



Configuring Network Time and Time Zone Settings

- [Adding NTP Server and Configuring Time Zone, on page 1](#)
- [Adding an NTP Server, on page 1](#)
- [Removing an NTP Server, on page 2](#)
- [Setting an NTP Server as the Preferred Server, on page 2](#)
- [Changing the Time Zone, on page 3](#)

Adding NTP Server and Configuring Time Zone

You must add an NTP server to your Cisco Unified SIP Proxy system and configure the time zone to ensure that system processes have the correct date and time associated with them.

Adding an NTP Server



Restriction

You can have a maximum of three NTP servers.

Procedure

Step 1 Choose **System > Network Time & Time Zone Settings**.

The system displays the Network Time & Time Zone Settings page.

Step 2 Click **Add**.

The system displays the Add a NTP Server page.

Step 3 Enter the hostname or IP address of the NTP server. To make it the primary NTP server, check the **Preferred** check box.

Step 4 Click **Add**.

The system displays the Network Time and Time Zone Settings page with the new server listed in the table.

What to do next

Save the configuration. See [Managing the System Configuration](#).

Reload the configuration. See [Using the Administration Control Panel](#).

Related Topics

[Using the Administration Control Panel](#)

[Managing the System Configuration](#)

Removing an NTP Server

Procedure

Step 1 Choose **System > Network Time & Time Zone Settings**.

The system displays the Network Time & Time Zone Settings page.

Step 2 Check the check box next to the NTP server to remove.**Step 3** Click **Delete**.**Step 4** Click **OK** at the prompt.

What to do next

Save the configuration. See [Managing the System Configuration](#).

Reload the configuration. See [Using the Administration Control Panel](#).

Related Topics

[Using the Administration Control Panel](#)

[Managing the System Configuration](#)

Setting an NTP Server as the Preferred Server



Restriction You must have at least two NTP servers.

Procedure

Step 1 Choose **System > Network Time & Time Zone Settings**.

The system displays the Network Time & Time Zone Settings page.

- Step 2** Check the check box next to the NTP server to set as the preferred server.
- Step 3** Click **Preferred**.
- Step 4** Click **OK**.
-

What to do next

Save the configuration. See [Managing the System Configuration](#).

Reload the configuration. See [Using the Administration Control Panel](#).

Related Topics

- [Using the Administration Control Panel](#)
- [Managing the System Configuration](#)

Changing the Time Zone

Procedure

- Step 1** Choose **System > Network Time & Time Zone Settings**.
The system displays the Network Time & Time Zone Settings page.
- Step 2** Use the drop-down menu to select the correct country.
- Step 3** Use the drop-down menu to select the correct time zone.
- Step 4** Click **Apply**.
- Step 5** Click **OK** at the information prompt.
-

What to do next

Save the configuration. See [Managing the System Configuration](#).

Reload the configuration. See [Using the Administration Control Panel](#).

Related Topics

- [Using the Administration Control Panel](#)
- [Managing the System Configuration](#)

