



Use the Administration Control Panel for Cisco Unified Communications Manager (CUCME)

- [Save Cisco Unified Communications Manager Express, on page 1](#)
- [Create Cisco Unified CME Configuration Files, on page 1](#)
- [Switch the Call Agent to Cisco Unified Communications Manager, on page 2](#)
- [Save or Reload Cisco Unity Express, on page 2](#)

Save Cisco Unified Communications Manager Express

Use this procedure to save Cisco Unified CME.

Step 1 Choose **Administration > Control Panel**.

Step 2 Under the Cisco Unified Communications Manager Express label, click **Save Configuration**.

Step 3 Click Ok at the prompt.

To create Cisco Unified CME configuration files, see [Create Cisco Unified CME Configuration Files, on page 1](#). To save or reload Cisco Unity Express, see [Save or Reload Cisco Unity Express, on page 2](#). To switch the call agent to Cisco Unified Communications Manager, see [Switch the Call Agent to Cisco Unified Communications Manager, on page 2](#).

Create Cisco Unified CME Configuration Files

Cisco Unified CME configuration files are eXtensible Markup Language (XML) configuration files that are required for IP phones. When new IP phones are added in CME, the new configuration files need to be created.

Use this procedure to create Cisco Unified CME configuration files.

Step 1 Choose **Administration > Control Panel**.

Step 2 Under the Cisco Unified Communications Manager Express label, click **Create CNF Files**.

A confirmation dialog box will appear if the configuration files are created successfully.

To save Cisco Unified Communications Manager Express, see [Save Cisco Unified Communications Manager Express, on page 1](#). To save or reload Cisco Unity Express, see [Save or Reload Cisco Unity Express, on page 2](#). To switch the call agent to Cisco Unified Communications Manager, see [Switch the Call Agent to Cisco Unified Communications Manager, on page 2](#).

Switch the Call Agent to Cisco Unified Communications Manager

Use this procedure to switch the call agent to Cisco Unified Communications Manager.

Step 1 Choose **Administration > Control Panel**.

Step 2 Under the Call Agent Integration: CUCME label, click **Switch to CUCM**.

A warning box appears indicating:

“Warning: This operation will a. permanently delete all non-local site related configuration b. reboot the system automatically Do you wish to continue?”

Step 3 Click **Ok** to switch to Cisco Unified Communications Manager or click **Cancel**.

To save Cisco Unified Communications Manager Express, see [Save Cisco Unified Communications Manager Express, on page 1](#). To create Cisco Unified CME configuration files, see [Create Cisco Unified CME Configuration Files, on page 1](#). To save or reload Cisco Unity Express, see [Save or Reload Cisco Unity Express, on page 2](#).

Save or Reload Cisco Unity Express

Use this procedure to save or reload Cisco Unity Express.

Step 1 Choose **Administration > Control Panel**.

Step 2 Under the Cisco Unity Express - Administration label, click **Save Configuration**.

Step 3 Click **Ok** at the prompt.

Step 4 Click **Reload Cisco Unity Express**. A dialog box appears warning you that reloading the system will terminate all end user sessions and that any unsaved configuration data will be lost.

Step 5 Click **Ok** or **Cancel** to complete the task.

To save Cisco Unified Communications Manager Express, see [Save Cisco Unified Communications Manager Express, on page 1](#). To create Cisco Unified CME configuration files, see [Create Cisco Unified CME Configuration Files, on page 1](#). To switch the call agent to Cisco Unified Communications Manager, see [Switch the Call Agent to Cisco Unified Communications Manager, on page 2](#).
