



show diameter-hdd-module

This chapter includes the **show diameter-hdd-module** command output tables.

- [show diameter-hdd-module file-space-usage](#), on page 1
- [show diameter-hdd-module statistics](#), on page 1

show diameter-hdd-module file-space-usage

Table 1: show diameter-hdd-module file-space-usage Command Output Descriptions

| Field | Description |
|--|---|
| CDRMOD Instance Id | The CDRMOD instance identifier. |
| Diameter-hdd-module File Storage LIMIT | Displays the configured storage limit for Diameter files. |
| Diameter-hdd-module File Storage USAGE | Displays the hard disk space utilized for the Diameter files. |
| Percentage of Diameter-hdd-module file store usage | Displays the percentage of hard-disk space utilized for the Diameter files. |

show diameter-hdd-module statistics

Table 2: show diameter-hdd-module statistics Command Output Descriptions

| Field | Description |
|---|---|
| Diameter-hdd-Module file Statistics | |
| CDRMOD Instance Id | The CDRMOD instance identifier. |
| Overall Statistics | |
| Diameter-hdd-module files rotated | Total number of Diameter files rotated. |
| Diameter-hdd-module files rotated due to volume limit | Total number of Diameter files rotated due to volume limit. |

| Field | Description |
|--|--|
| Diameter-hdd-module files rotated due to time limit | Total number of Diameter files rotated due to time limit. |
| Diameter-hdd-module files rotated due to tariff-time | Total number of Diameter files rotated due to tariff time. |
| Diameter-hdd-module files rotated due to records limit | Total number of Diameter files rotated because of record limits. |
| Diameter-hdd-module file rotation failures | Total number of times rotation failed for Diameter file. |
| Diameter-hdd-module files deleted | Total number of Diameter files deleted. |
| Diameter-hdd-module records deleted | Total number of Diameter records deleted. |
| Diameter-hdd-module records received | Total number of Diameter records received by the service. |
| Current open Diameter-hdd-module files | Total number of Diameter files that are currently open. |
| Time of last Diameter-hdd-module file deletion | Date and time of last Diameter file deleted. |
| Diameter-hdd-module PUSH Statistics | |
| Overall Statistics | |
| Primary Server Statistics | |
| Secondary Server Statistics | |
| Successful File Transfers | Total number of successful file transfers. |
| Failed File Transfers | Total number of failed file transfers. |
| Num of times PUSH initiated | Total number of times a Diameter-hdd push attempt was initiated. |
| Num of times PUSH Failed | Total number of times a Diameter-hdd push attempt failed. |
| Num of times PUSH cancelled due to HD failure | Total number of times a Diameter-hdd push was cancelled due to hard disk failures. |
| Num of periodic PUSH | Total number of periodic push. |
| Num of manual PUSH | Total number of manual push. |
| Current status of PUSH | Indicates the current status of push – Running/Not Running. |
| Last completed PUSH time | The date and time the last push completed. |