



## Log Manager

To access Log management tasks, log into the system (see “[Logging In and Out](#)” section on page 2-1). Then, from the Home page, click the **Tools** tab. The Tools page appears.

From the Tools Page, click **Log Manager**. The Log Manager page appears showing:

- View Logs
- Clear Logs
- Export Logs

## Viewing Log Files

- Step 1** From the Log Manager page, click **View Logs**.  
The View Log Files dialog box appears (see [Figure 14-1](#)).

**Figure 14-1 Log File Viewer**

### View Log Files

Select Log File:  Events log  Config Server log  HTTP Server log  Access log  Cron Tab  Authentication Errors  PIX Log  Image Server log  IMGW log

Number of lines: 25

Filter String:

View

- Step 2** Choose the log file you want to view.  
[Table 14-1](#) shows valid values for these fields.

**Table 14-1 Valid Values for View Log Files**

Attribute	Description	Valid Values
Select Log Files	List of available log files.	Radio button
Number of lines	Number of lines displayed.	
Filter String	Filter string	a-z A-Z 0-9 -(hyphen) _ (under-score) (period)


- Step 3** Set the number lines you want to display.
- Step 4** To limit the report to display only specific entries, set a case-sensitive keyword filter, or leave blank.
- Step 5** Click **View**.  
A report displays.

## Clearing Logs

- Step 1** From the Log Manager page, click **Clear Logs**.  
The Clear Log Files dialog box appears (see [Figure 14-1](#)).

**Figure 14-2 Clear Logs**

### Clear Logs



- Step 2** Check the log files you want to clear.
- Step 3** To cancel this task, click **Cancel**.
- Step 4** To clear the selected log files, click **Clear**.

# Exporting Logs

- Step 1** From the Log Manager page, click **Export Logs**.  
The Export Log Files dialog box appears (see [Figure 14-3](#)).

**Figure 14-3** Export Logs

## Export Logs

Select Log File:

- Events Log
- Config Server Log
- HTTP Server Log
- Access Log
- Cron Tab
- Authentication Errors
- PIX Log
- Image Server Log
- IMGW Log

Clear logs after export.

Export Cancel

129342

- Step 2** Check the log files you want to export.
- Step 3** To clear logs after export, check the check box.
- Step 4** To cancel this task, click **Cancel**.
- Step 5** To export the selected log files, click **Export**.

