



Log Manager

To access Log management tasks, log into the system (see “[Logging In and Out](#)” section on page 2-1). Then, from the Home page, click the **Tools** tab. The Tools page appears.

From the Tools Page, click **Log Manager**. The Log Manager page appears showing:

- View Logs
- Clear Logs
- Export Logs

Viewing Log Files

- Step 1** From the Log Manager page, click **View Logs**.
The View Log Files dialog box appears (see [Figure 14-1](#)).

Figure 14-1 Log File Viewer

View Log Files

Select Log File: Events log Config Server log HTTP Server log Access log Cron Tab Authentication Errors PIX Log Image Server log IMGW log

Number of lines: 25

Filter String:

129335

- Step 2** Choose the log file you want to view.
[Table 14-1](#) shows valid values for these fields.

Table 14-1 Valid Values for View Log Files

Attribute	Description	Valid Values
Select Log Files	List of available log files.	Radio button
Number of lines	Number of lines displayed.	
Filter String	Filter string	a-z A-Z 0-9 -(hyphen) _ (under-score) (period)


- Step 3** Set the number lines you want to display.
- Step 4** To limit the report to display only specific entries, set a case-sensitive keyword filter, or leave blank.
- Step 5** Click **View**.
A report displays.

Clearing Logs

- Step 1** From the Log Manager page, click **Clear Logs**.
The Clear Log Files dialog box appears (see [Figure 14-1](#)).

Figure 14-2 Clear Logs

Clear Logs



- Step 2** Check the log files you want to clear.
- Step 3** To cancel this task, click **Cancel**.
- Step 4** To clear the selected log files, click **Clear**.

Exporting Logs

- Step 1** From the Log Manager page, click **Export Logs**.
The Export Log Files dialog box appears (see [Figure 14-3](#)).

Figure 14-3 Export Logs

Export Logs

Select Log File:

- Events Log
- Config Server Log
- HTTP Server Log
- Access Log
- Cron Tab
- Authentication Errors
- PIX Log
- Image Server Log
- IMGW Log

Clear logs after export.

Export Cancel

129342

- Step 2** Check the log files you want to export.
- Step 3** To clear logs after export, check the check box.
- Step 4** To cancel this task, click **Cancel**.
- Step 5** To export the selected log files, click **Export**.

