



Planning Guide for Cisco Jabber 11.6

First Published: 2016-04-20

Americas Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: [www.cisco.com go trademarks](http://www.cisco.com/go/trademarks). Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)

© 2018 Cisco Systems, Inc. All rights reserved.



New and Changed Information

- [New and Changed Information](#), on page iii

New and Changed Information

Description of Change	Date	Where Documented
Requirements for IPv6	April 20, 2016	IPv6 Requirements , on page 17



CONTENTS

PREFACE

New and Changed Information	iii
New and Changed Information	iii

CHAPTER 1

Jabber Overview	1
Purpose of this Guide	1
About Cisco Jabber	1
Planning Checklist	2
Supported Languages	2

CHAPTER 2

Requirements	5
Server Requirements	5
Operating System Requirements	6
Operating Systems for Cisco Jabber for Windows	6
Operating Systems for Cisco Jabber for Mac	7
Operating Systems for Cisco Jabber for Android	7
Operating Systems for Cisco Jabber for iPhone and iPad	8
Hardware Requirements	8
Hardware Requirements for Desktop Clients	8
CTI Supported Devices	9
Hardware Requirements for Cisco Jabber for Android	9
Hardware Requirements for Cisco Jabber for iPhone and iPad	15
Network Requirements	16
IPv6 Requirements	17
Requirements to Support IPv6 in Android	20
Windows	20
Supported Codecs	24

Virtual Environment Requirements	25
Audio and Video Performance Reference	25
Audio Bit Rates for Cisco Jabber Desktop Clients	25
Audio Bit Rates for Cisco Jabber Mobile Clients	25
Video Bit Rates for Cisco Jabber Desktop Clients	26
Video Bit Rates for Cisco Jabber for Android	26
Video Bit Rates for Cisco Jabber for iPhone and iPad	27
Presentation Video Bit Rates	27
Maximum Negotiated Bit Rate	28
COP Files	28
Bandwidths	29
Bandwidth Performance Expectations for Cisco Jabber Desktop Clients	29
Bandwidth Performance Expectations for Cisco Jabber for Android	30
Bandwidth Performance Expectations for Cisco Jabber for iPhone and iPad	30
Video Rate Adaptation	31

CHAPTER 3

Deployment Scenarios	33
On-Premises Deployment	33
On-Premises Deployment with Cisco Unified Communications Manager IM and Presence Service	33
Computer Telephony Integration	34
On-Premises Deployment in Phone Mode	35
Softphone	36
Deskphone	36
Extend and Connect	36
Cloud-Based Deployments	36
Cloud-Based Deployment	37
Hybrid Cloud-Based Deployment	37
Deployment in a Virtual Environment	38
Virtual Environment and Roaming Profiles	39
Remote Access	40
Expressway for Mobile and Remote Access	40
Supported Services	40
Cisco AnyConnect Deployments	46

Deployment with Single Sign-On	47
Single Sign-On Requirements	48
Single Sign-On and Remote Access	49

CHAPTER 4

User Management 51

Jabber IDs	51
IM Address Scheme	52
Service Discovery using Jabber IDs	52
SIP URI	53
LDAP User ID	53
User ID Planning for Federation	53
Proxy Addresses for User Contact Photos	53
Authentication and Authorization	53
Cisco Unified Communications Manager LDAP Authentication	53
Cisco Webex Messenger Login Authentication	54
Single Sign-On Authentication	54
Voicemail Authentication	54
Multiple Resource Login	54

CHAPTER 5

Service Discovery 55

How the Client Connects to Services	55
Cisco Webex Service Discovery	55
Cisco Intercluster Lookup Service	56
Expressway for Mobile and Remote Access Service Discovery	56
Recommended Connection Methods	56
Sources of Authentication	58
How the Client Locates Services	59
Method 1: Search For Services	60
How the Client Discovers Available Services	60
Client Issues an HTTP Query	62
Client Queries the Name Server	62
Client Connects to Internal Services	63
Client Connects through Expressway for Mobile and Remote Access	64
Cisco UDS SRV Record	65

Collaboration Edge SRV Record	67
DNS Configuration	68
How the Client Uses DNS	68
Domain Name System Designs	69
Method 2: Customization	72
Service Discovery Customization	72
Custom Installations for Cisco Jabber for Windows	72
Custom Installations for Cisco Jabber for Mac, iPhone and iPad, and Android	73
Method 3: Manual Installations	73
High Availability	74
High Availability for Instant Messaging and Presence	74
Client Behavior During a Failover	74
High Availability for Voice and Video	76
Survivable Remote Site Telephony	76
Configuration Priorities	76
Group Configurations Using Cisco Support Field	77

CHAPTER 6
Contact Source 79

Directory Servers	79
What is a Contact Source?	80
When to Configure Directory Integration	80
Why Do I Need a Contact Source?	81
Contact Source Options	81
LDAP Options: EDI and BDI	81
Enhanced Directory Integration	81
Basic Directory Integration	83
Cisco Unified Communications Manager User Data Service	84
Contact Resolution with Multiple Clusters	85
LDAP Prerequisites	85
LDAP Service Account	86
Jabber ID Attribute Mapping	86
Search Jabber IDs	86
Local Contact Sources	87
Custom Contact Sources	87

Contact Caching	87
Dial Plan Mapping	87
Cisco Unified Communication Manager UDS for Mobile and Remote Access	88
Cloud Contact Source	88
Cisco Webex Contact Source	88
Contact Photo Formats and Dimensions	88
Contact Photo Formats	88
Contact Photo Dimensions	89
Contact Photo Adjustments	89

CHAPTER 7

Security and Certificates 91

Encryption	91
Compliance and Policy Control for File Transfer and Screen Capture	91
Instant Message Encryption	91
On-Premises Encryption	91
Cloud-Based Encryption	92
Encryption Icons	94
Local Chat History	95
Voice and Video Encryption	95
Federal Information Processing Standards	95
Secure LDAP	96
Certificates	97
Certificate Validation	97
Required Certificates for On-Premises Servers	98
Certificate Signing Request Formats and Requirements	98
Revocation Servers	99
Server Identity in Certificates	99
Certificates for Multiserver SANs	100
Certificate Validation for Cloud Deployments	100

CHAPTER 8

Screen Share 103

Screen Share	103
Cisco Webex Screen Share	103
BFCP Screen Share	103

IM Only Screen Share	104
Escalate to a Meeting and Share	104

CHAPTER 9

Federation	105
Interdomain Federation	105
Intradomain Federation	106
User ID Planning for Federation	106



CHAPTER 1

Jabber Overview

- [Purpose of this Guide, on page 1](#)
- [About Cisco Jabber, on page 1](#)
- [Planning Checklist, on page 2](#)
- [Supported Languages, on page 2](#)

Purpose of this Guide

The *Cisco Jabber Planning Guide* includes the following information to assist you in planning the deployment and installation of Cisco Jabber.

- A product overview describing the features available in the product for this release
- Planning considerations for service discovery, encryption, and contact sources (Enhanced Directory Integration [EDI] and Basic Directory Integration [BDI]).
- Information about how you are going to deploy the client, whether it's an on-premises or cloud deployment.
- Requirements for hardware, software, network, and certificates.

To deploy and install Cisco Jabber, use the *Cisco Jabber Deployment and Installation Guide*.

About Cisco Jabber

Cisco Jabber is a suite of Unified Communications applications that allow seamless interaction with your contacts from anywhere. Cisco Jabber offers IM, presence, audio and video calling, voicemail, and conferencing.

The applications in the Cisco Jabber family of products are:

- Cisco Jabber for Android
- Cisco Jabber for iPhone and iPad
- Cisco Jabber for Mac
- Cisco Jabber for Windows

For more information about the Cisco Jabber suite of products, see <https://www.cisco.com/go/jabber>.

Planning Checklist

Use this checklist to plan your Cisco Jabber Deployment.

Task	See	Completed?
Confirm that your servers, hardware, and network comply with the requirements.	Requirements, on page 5	
Determine how you plan to deploy Cisco Jabber.	Deployment Scenarios, on page 33	
Plan your user management.	User Management, on page 51	
Review Service Discovery to determine if you plan to configure service discovery and to determine which service discovery records you require.	Service Discovery, on page 55	
Determine how you plan to configure your contact source.	Contact Source, on page 79	
Confirm that you have the required certificates and security based on the deployment option you select.	Security and Certificates, on page 91	
Review the available screen share options.	Screen Share, on page 103	
Review the federation available for your deployment.	Federation, on page 105	

Supported Languages

The following table lists the Locale Identifier (LCID) or Language Identifier (LangID) for the languages that the Cisco Jabber clients support.

Supported Languages	Cisco Jabber for Windows	Cisco Jabber for Mac	Cisco Jabber for Android, Cisco Jabber for iPhone and iPad	LCID/LangID
Arabic - Saudi Arabia	X		X	1025
Bulgarian - Bulgaria	X	X		1026
Catalan - Spain	X	X		1027
Chinese (Simplified) - China	X	X	X	2052
Chinese (Traditional) - Taiwan	X	X	X	1028

Supported Languages	Cisco Jabber for Windows	Cisco Jabber for Mac	Cisco Jabber for Android, Cisco Jabber for iPhone and iPad	LCID/LangID
Croatian - Croatia	X	X		1050
Czech - Czech Republic	X	X		1029
Danish - Denmark	X	X	X	1030
Dutch - Netherlands	X	X	X	1043
English - United States	X	X	X	1033
Finnish - Finland	X	X		1035
French - France	X	X	X	1036
German - Germany	X	X	X	1031
Greek - Greece	X	X		1032
Hebrew - Israel	X			1037
Hungarian - Hungary	X	X		1038
Italian - Italy	X	X	X	1040
Japanese - Japan	X	X	X	1041
Korean - Korea	X	X	X	1042
Norwegian - Norway	X	X		2068
Polish - Poland	X	X		1045
Portuguese - Brazil	X	X	X	1046
Portuguese - Portugal	X	X		2070
Romanian - Romania	X	X		1048
Russian - Russia	X	X	X	1049
Serbian	X	X		1050
Slovak - Slovakian	X	X		1051
Slovenian - Slovenia	X	X		1060

Supported Languages	Cisco Jabber for Windows	Cisco Jabber for Mac	Cisco Jabber for Android, Cisco Jabber for iPhone and iPad	LCID/LangID
Spanish - Spain (Modern Sort)	X	X	X	3082
Swedish - Sweden	X	X	X	5149
Thai - Thailand	X	X		1054
Turkish	X	X		1055



CHAPTER 2

Requirements

- [Server Requirements, on page 5](#)
- [Operating System Requirements, on page 6](#)
- [Hardware Requirements, on page 8](#)
- [Network Requirements, on page 16](#)
- [Virtual Environment Requirements, on page 25](#)
- [Audio and Video Performance Reference, on page 25](#)

Server Requirements

The following software requirements are common to all Cisco Jabber clients in this release:

Service	Software Requirement	Supported Version
IM and Presence	Cisco Unified Communications Manager IM and Presence Service	9.x and later
	Cisco WebEx Messenger	
Telephony	Cisco Unified Communications Manager	9.x and later
	Cisco Unified Survivable Remote Site Telephony	8.5 and later
Contact Search	LDAP directory	LDAP v3 compliant directory such as Microsoft Active directory 2008 R2 and Open LDAP 2.4 or later
Voicemail	Cisco Unity Connection	8.6(2)* and later

Service	Software Requirement	Supported Version
Conferencing	Cisco TelePresence Server	3.1 and later
	Cisco TelePresence MCU	4.3 and later
	Cisco ISR PVDM3	Cisco Unified Communications Manager 9.x and later
	Cloud CMR	Cisco WebEx Meetings Server with Collaboration Meeting Room
	Cisco WebEx Meetings Server	2.0 and later Cisco Jabber for Windows supports 1.5 and later
	Cisco WebEx Meeting Center	WBS29 and later
	Cisco WebEx Meetings Client Only applies to Cisco Jabber for Android.	4.5 and later
Remote Access	Cisco Adaptive Security Appliance Only applies to Cisco Jabber for Android.	8.4(1) and later
	Cisco AnyConnect Secure Mobility Client Cisco Jabber for Android and Cisco Jabber for iPhone and iPad clients only.	Platform-dependent
	Cisco Expressway C	8.1.1 and later
	Cisco Expressway E	8.1.1 and later

Cisco Jabber uses domain name system (DNS) servers during startup, DNS servers are mandatory for Cisco Jabber setup.

Operating System Requirements

Operating Systems for Cisco Jabber for Windows

You can install Cisco Jabber for Windows on the following operating systems:

- Microsoft Windows 10 (desktop mode)
- Microsoft Windows 8.1 (desktop mode)
- Microsoft Windows 8 (desktop mode)

- Microsoft Windows 7

Cisco Jabber for Windows does not require the Microsoft .NET Framework or any Java modules.

For Microsoft Windows 7 or 8.x, you can download Cisco Media Services Interface (MSI) 4.1.2 for use with deskphone video.

Windows 10 Servicing Options

Cisco Jabber for Windows supports the following Windows 10 servicing options:

- Current Branch (CB)
- Current Branch for Business (CBB)
- Long-Term Servicing Branch (LTSB)—with this option, it is your responsibility to ensure that any relevant service updates are deployed.

For more information about Windows 10 servicing options, see the following Microsoft documentation: [https://technet.microsoft.com/en-us/library/mt598226\(v=vs.85\).aspx](https://technet.microsoft.com/en-us/library/mt598226(v=vs.85).aspx).



Note

Cisco Jabber installs the required files to the following directories by default:

- %temp%\Cisco Systems\Cisco Jabber-Bootstrap.properties file and installation log
 - %LOCALAPPDATA%\Cisco\Unified Communications-Logs and temporary telemetry data
 - %APPDATA%\Cisco\Unified Communications-Cached configurations and account credentials
 - %ProgramFiles%\Cisco Systems\Cisco Jabber-Installation files for x86 Windows
 - %ProgramFiles(x86)%\Cisco Systems\Cisco Jabber-Installation files for x64 Windows
-

Operating Systems for Cisco Jabber for Mac

You can install Cisco Jabber for Mac on the following operating systems:

- Apple OS X El Capitan 10.11 (or later)
- Apple OS X Yosemite 10.10 (or later)
- Apple OS X Mavericks 10.9 (or later)

Operating Systems for Cisco Jabber for Android

Cisco Jabber for Android supports Android OS 4.4 or later version. For information on the OS that is required to install Cisco Jabber for Android, see the section *Hardware Requirements for Cisco Jabber for Android*.



Note If Cisco Jabber is installed on Android 6.0 Marshmallow OS or later, and if it is kept idle:

- The network connection to Cisco Jabber is disabled.
- The users do not receive any calls or messages.

Tap **Change Settings** and ignore battery optimization to receive calls and messages.

Operating Systems for Cisco Jabber for iPhone and iPad

Cisco Jabber for iPhone and iPad supports the following operating systems:

- iOS 10 and above
- watchOS 3 and watch OS 4



Important Cisco supports only the current App Store version of Cisco Jabber for iPhone and iPad. Defects found in any Cisco Jabber for iPhone and iPad release are evaluated against current versions.

Hardware Requirements

Hardware Requirements for Desktop Clients

Requirement	Cisco Jabber for Windows	Cisco Jabber for Mac
Installed RAM	2-GB RAM on Microsoft Windows 7 and Windows 8	2-GB RAM
Free physical memory	128 MB	1 GB
Free disk space	256 MB	300 MB

Requirement	Cisco Jabber for Windows	Cisco Jabber for Mac
CPU speed and type	AMD Mobile Sempron Processor 3600+ 2 GHz Intel Core 2 Duo Processor T7400 @ 2.16 GHz	Intel Core 2 Duo or later processors in any of the following Apple hardware: <ul style="list-style-type: none"> • Mac Pro • MacBook Pro (including Retina Display model) • MacBook • MacBook Air • iMac • Mac Mini
GPU	DirectX11 on Microsoft Windows 7	N/A
I/O ports	USB 2.0 for USB camera and audio devices.	USB 2.0 for USB camera and audio devices

CTI Supported Devices

To view the list of Computer Telephony Integration (CTI) supported devices: From Cisco Unified Reporting, select **Unified CM Phone Feature List**. From the **Feature** drop-down list, select **CTI controlled**.

Hardware Requirements for Cisco Jabber for Android

The minimum OS, CPU, and display requirements for the Android devices are:

- Android Operating System—4.1.2 or later.
- CPU—1.5 GHz dual-core, 1.2 GHz quad-core or higher (quad-core recommended).
- Display—For two-way video, the minimum display resolution requirement is 480 x 800 or higher.



Note

- Cisco Jabber for Android is not supported on Android devices that are based on an Intel chipset.
- Cisco Jabber for Android does not support the Tegra 2 chipset.
- Due to an Android kernel issue, Cisco Jabber cannot register to the Cisco Unified Communications Manager on some Android devices. If this problem occurs, see the Troubleshooting chapter of the *Cisco Jabber for Android User Guide*.

Android Devices with IM Only Mode

Cisco Jabber for Android supports IM only mode on all Android devices that meet the following minimum specifications:



Note Cisco Jabber for Android is not supported on Android devices that are based on an Intel chipset.

Requirements	Description
Android OS	4.1.2 or later
CPU	1.5 GHz dual-core, 1.2 GHz quad-core or later (quad-core is recommended).
Display	320 x 480 or higher

Android Devices with Audio and Video Enabled Mode



Note Cisco Jabber for Android is tested with the Android devices listed here. Although other Android devices are not officially supported, you might be able to use Cisco Jabber for Android on other Android devices.

Cisco Jabber for Android supports Audio and Video Enabled mode in the following devices with respective version of Operating System provided in the table:

Table 1: Other Devices

Device	Device Model	Operating System
Cisco DX	70	10.2.x version
	80	10.2.x version
	650	10.2.x version
HTC	M7	Android OS 4.4.2 or later
	M8	Android OS 4.4.2 or later
	M9	Android OS 5.0 or later
	One Max	Android OS 4.4.2 or later
	E9 PLUS	Android OS 5.0.2 or later

Device	Device Model	Operating System
Google Nexus	4	Android OS 5.1.1 or later
	5	Android OS 4.4 or later
	6	Android OS 5.0.2 or later
	6P ¹	Android OS 6.0 or later
	7	Android OS 4.4 or later
	9	Android OS 5.0.2 or later
	10	Android OS 4.4 or later
	5X	Android OS 6.0 or later
	Pixel C	Android OS 6.0 or later
LG	G2	Android OS 4.2.2 or later
	G3	Android OS 4.4.2 or later
	G4	Android OS 5.1 or later
	V10	Android OS 5.0 or later
	Optimus G Pro	Android OS 4.4.2 or later
Symbol	Moto G	Android OS 4.4.2 or later
	MC40 ²	Android OS 4.1.1 or later
Sony Xperia ³	ZR/A	Android OS 4.1.2 or later
	M2	Android OS 4.3 or later
	Z1	Android OS 4.2 or later
	Z2	Android OS 4.4.2 or later
	Z2 tablet	Android OS 4.4.2 or later
	Z3	Android OS 4.4.2 or later
	Z3 Tablet Compact	Android OS 4.4.4 or later
	Z3+/Z4 ⁴	Android OS 5.0.2 or later
	Z4 TAB	Android OS 5.0 or later
	Z5 Premium and Z5	Android OS 5.0.2 or later

Device	Device Model	Operating System
Huawei ⁵	G6	Android OS 4.2.2 or later
	Mate 7	Android OS 4.4 or later
	P8	Android OS 4.4.4 or later
	Honor7	Android OS 5.0 or later
Sonim	XP7	Android OS 4.4.4
Xiaomi	Mi 4	Android OS 4.4 or later
	Mi Note	Android OS 4.4.4 or later
	Mi Pad	Android OS 4.4.4 or later
Fujitsu	Arrows M305	Android OS 4.4.2 or later
	Arrows M555	Android OS 4.4.2 or later
Honeywell Dolphin	CT50	Android OS 4.4.4 or later
BlackBerry	Priv	Android OS 5.1 or later

¹ If your device OS is 6.0 or 6.0.1, and you use Jabber in the corporate network, then contact your administrator to set your Jabber phone service as a secure phone service, or your phone will not respond. For more information, see the [Android developer link](#).

² Cisco Jabber supports only audio mode with MC40 device. Cisco Jabber does not support launching WebEx Meeting from MC40 device.

³ There is a limitation that Sony devices with Android OS 6.0 cannot play voicemail in Jabber.

⁴ Video call is unstable on Sony Z3+/Z4, you can disable your self-video for a video call or make a voice call only.

⁵ Jabber is made inactive due to the high power consumption on Huawei devices.

Cisco Jabber for Android supports Audio and Video Enabled mode in all Samsung devices that meet minimal hardware requirement. These Samsung devices are tested and qualified:

Table 2: Samsung Devices

Samsung Galaxy	Operating System
A7	Android OS 4.4.4 or later
A8	Android OS 5.1.1 or later
Rugby Pro	Android OS 4.2.2 or later
Xcover3	Android OS 4.4.4 or later
Note II	Android OS 4.2 or later
Note III	Android OS 4.3 or later
Note IV	Android OS 4.4.4 or later

Samsung Galaxy	Operating System
Note 5	Android OS 5.1.1 or later
Note Edge	Android OS 4.4.4 or later
SII	Android OS 4.1.2 or later
SIII	Android OS 4.2.2 or later
S4	Android OS 4.2.2 or later
S4 mini	Android OS 4.2.2 or later
S5	Android OS 4.2.2 or later
S5 mini	Android OS 4.2.2 or later
S6	Android OS 5.0.2 or later
S6 Edge	Android OS 5.0.2 or later
S6 Edge+	Android OS 5.1.1 or later
Tab 4 7-inch, 8-inch, and 10.1-inch	Android OS 4.4.2 or later
Tab PRO 8.4-inch and 10.1-inch	Android OS 4.4.2 or later
Tab S 8.4-inch & 10.5-inch	Android OS 4.4.2 or later
Tab 3 8-inch	Android OS 4.4 or later
Note Pro 12.2	Android OS 4.4.2 or later
Note 10.1-inch 2014 Edition	Android OS 4.4.2 or later

Android Version Support Policy for Cisco Jabber for Android

Due to an Android kernel issue, Cisco Jabber cannot register to the Cisco Unified Communications Manager on some Android devices. To resolve this problem, try the following:

- Upgrade the Android kernel to 3.10 or later version.
- Set the Cisco Unified Communications Manager to use mixed mode security, enable secure SIP call signaling, and use port 5061. See the *Cisco Unified Communications Manager Security Guide* for your release for instructions on configuring mixed mode with the Cisco CTL Client. You can locate the security guides in the Cisco Unified Communications Manager [Maintain and Operate Guides](#). This solution applies to the following supported devices:

Device Model	Operating System
HTC M7	Android OS 4.4.2 or later
HTC M8	Android OS 4.4.2 or later
HTC M9	Android OS 5.0 or later

Device Model	Operating System
HTC One Max	Android OS 4.4.2 or later
Sony Xperia M2	Android OS 4.3 or later and kernel version earlier than 3.10.49. ⁶
Sony Xperia Z1	
Sony Xperia ZR/A	
Sony Xperia Z2	
Sony Xperia Z2 tablet	
Sony Xperia Z3	
Sony Xperia Z3 Tablet Compact	
Xiaomi Mi4	(Android OS 4.4 or later)
Xiaomi Mi Note	(Android OS 4.4.4 or later)
Xiaomi Mi Pad	(Android OS 4.4.4 or later)
Sonim XP7	(Android OS 4.4.4)
Honeywell Dolphin CT50	Android OS 4.4.4 or later

⁶ If Sony device's android OS is 5.0.2 or higher and kernel version is 3.10.49 or higher, then it can support non-secure mode.

Supported Bluetooth Devices

Bluetooth Devices	Useful Information
Jabra Motion	Upgrade Jabra Motion Bluetooth headset to firmware version 3.72 or above. The Jabra Motion Bluetooth headsets with firmware version 3.72 or above supports Cisco Jabber call control.
Jawbone ICON for Cisco Bluetooth Headset	If you use a Samsung Galaxy S4, you can experience problems due to compatibility issues between these devices.
Plantronics BackBeat 903+	If you use a Samsung Galaxy S4, you can experience problems due to compatibility issues between these devices.
Jabra Wave+	
Jabra Biz 2400	
Jabra Easygo	

Bluetooth Devices	Useful Information
Jabra PRO 9470	
Jabra Speak 510	
Jabra Supreme UC	
Jabra Stealth	
Jabra Evolve 65 UC Stereo	
Plantronics Voyager Legend	
Plantronics Voyager Legend UC	
Plantronics Voyager edge UC	
Plantronics Voyager edge	
Plantronics PLT focus	



Note Using a Bluetooth device on a Samsung Galaxy SIII can cause distorted ringtone and call audio.

Supported Android Wear

Cisco Jabber is supported on all Android wear, which has Android OS 5.0 or later and Google service 8.3 or later. Cisco Jabber is tested on these Android Wear devices:

- Samsung Gear live
- LG G Watch R
- Sony SmartWatch 3
- LG Watch Urbane
- Moto 360
- Moto 360 (2nd Gen)
- Huawei watch

Hardware Requirements for Cisco Jabber for iPhone and iPad

The following Apple devices are supported for Cisco Jabber for iPhone and iPad on iOS 10.X and later. The devices that are not upgraded to iOS 10 are not supported.

Apple Device	Generation
iPod touch	5 and 6

Apple Device	Generation
iPhone	5, 5c, 5s, 6, 6 Plus, iPhone SE , 6s, and 6s Plus and Apple Watch
iPad	Third, fourth, 12.9 inch iPad Pro and 9.7 inch iPad Pro
iPad mini	Mini 2, mini 3, and mini 4
iPad Air	Air1 and Air 2

The following Bluetooth headsets are supported on iPhone and iPad:

Jabra Easygo	Jabra Speak 510
Jabra EXTREME 2	Jawbone ICON for Cisco Bluetooth Headset
Jabra Speak 450 for Cisco	Jabra Stealth
Jabra Supreme UC	Jabra Evolve 65 UC Stereo
Jabra Wave +	Plantronics Voyager Legend
Jabra Motion ⁷	Plantronics Voyager Legend UC
Sony Ericsson Bluetooth Headset BW600	Plantronics Voyager Edge
Jabra PRO 9470	Plantronics Voyager Edge UC
Jabra BIZ 2400	

⁷ Supports Bluetooth control for Cisco Jabber calls. This feature is only supported with firmware version 3.72.

Network Requirements

When using Cisco Jabber over your corporate Wi-Fi network, we recommend that you do the following:

- Design your Wi-Fi network to eliminate gaps in coverage as much as possible, including in areas such as elevators, stairways, and outside corridors.
- Ensure that all access points assign the same IP address to the mobile device. Calls are dropped if the IP address changes during the call.
- Ensure that all access points have the same service set identifier (SSID). Hand-off may be much slower if the SSIDs do not match.
- Ensure that all access points broadcast their SSID. If the access points do not broadcast their SSID, the mobile device may prompt the user to join another Wi-Fi network, which interrupts the call.

Conduct a thorough site survey to minimize network problems that could affect voice quality. We recommend that you do the following:

- Verify nonoverlapping channel configurations, access point coverage, and required data and traffic rates.
- Eliminate rogue access points.
- Identify and mitigate the impact of potential interference sources.

For more information, see the following documentation:

- The “VoWLAN Design Recommendations” section in the *Enterprise Mobility Design Guide*.
- The *Cisco Unified Wireless IP Phone 7925G Deployment Guide*.
- The *Capacity Coverage & Deployment Considerations for IEEE 802.11g* white paper.
- The *Solutions Reference Network Design (SRND)* for your Cisco Unified Communications Manager release.

IPv6 Requirements

Cisco Jabber is fully IPv6 ready, it works as normal in pure IPv6 and hybrid networks with the limitations listed in this section. Cisco Collaboration solutions does not currently fully support IPv6. For example, Cisco VCS Expressway for Mobile and Remote Access has limitations in pure IPv6 networks that require NAT64/DNS64 to be deployed in mobile carrier networks. Cisco Unified Communications Manager and Cisco Unified Communications Manager IM and Presence don't currently support HTTPS in pure IPv6 networks.

This feature is configured in Jabber using the IP_Mode parameter to set the protocol to IPv4, IPv6, or Two Stacks. Two Stacks is the default setting. The IP_Mode parameter can be included in the jabber-config.xml file, the bootstrap for Windows, and the URL configuration for Mac and Mobile clients.

The network IP protocol used by Jabber when connecting to services is determined by the following factors:

- The jabber-config.xml IP_Mode parameter.
- The client operating system IP capabilities.
- The server operating system IP capabilities.
- The availability of a DNS record for IPv4 and IPv6.
- Cisco Unified Communications Manager SIP setting for softphone devices configuration for IPv4, IPv6, or both. The SIP connection setting for softphone devices must match the Jabber IP_Mode parameter setting to make a successful connection.
- Underlying network IP capabilities.

On Cisco Unified Communications Manager, the IP capability is determined by generic server settings and device-specific settings. The following table lists the expected Jabber connections given the various settings, this list assumes that the DNS records for IPv4 and IPv6 are both configured.

When the Client OS, Server OS, and Jabber IP_Mode parameter are set to Two Stacks, Jabber will use either IPv4 or IPv6 address for connections with the server in accordance with RFC6555.

Client OS	Server OS	Jabber IP_Mode parameter	Jabber Connection outcome
IPv4 Only	IPv4 Only	IPv4-Only	IPv4 Connection
		IPv6-Only	Connection Failure
		Two Stacks	IPv4 Connection

Client OS	Server OS	Jabber IP_Mode parameter	Jabber Connection outcome
IPv4 Only	IPv6 Only	IPv4-Only	Connection Failure
		IPv6-Only	Connection Failure
		Two Stacks	Connection Failure
IPv6 Only	IPv4 Only	IPv4-Only	Connection Failure
		IPv6-Only	Connection Failure
		Two Stacks	Connection Failure
IPv6 Only	IPv6 Only	IPv4-Only	Connection Failure
		IPv6-Only	IPv6 Connection
		Two Stacks	IPv6 Connection
IPv4 Only	Two Stacks	IPv4-Only	IPv4 Connection
		IPv6-Only	Connection Failure
		Two Stacks	IPv4 Connection
IPv6 Only	Two Stacks	IPv4-Only	Connection Failure
		IPv6-Only	IPv6 Connection
		Two Stacks	IPv6 Connection
Two Stacks	IPv4 Only	IPv4-Only	IPv4 Connection
		IPv6-Only	Connection Failure
		Two Stacks	IPv4 Connection
Two Stacks	IPv6 Only	IPv4-Only	Connection Failure
		IPv6-Only	IPv6 Connection
		Two Stacks	IPv6 Connection
Two Stacks	Two Stacks	IPv4-Only	IPv4 Connection
		IPv6-Only	IPv6 Connection
		Two Stacks	IPv6 Connection

When you use Jabber in IPv6-Only mode, NAT64/DNS64 is required to connect to an IPv4 infrastructure. For example, when connecting to Cisco Webex Messenger service, Cisco VCS Expressway for Mobile and Remote Access, and Cisco Spark.

Desktop device support is available for IPv6-only on-premise deployments. All Jabber mobile devices must be configured as Two Stacks.

For more details about IPv6 deployment, see the [IPv6 Deployment Guide for Cisco Collaboration Systems Release 12.0](#).

Limitations

- **HTTPS Connectivity**
 - In an On-Premises deployment, Cisco Jabber supports IPv4 only and Two Stacks modes to connect to Cisco Unified Communications Manager and Cisco Unified Communications Manager IM and Presence Service. These servers do not currently support IPv6 HTTPS connections.

Cisco Jabber can connect using HTTPS to Cisco Unity Connection for Voicemail using IPv6 only mode.
- **Cisco Webex Messenger Limitations**
 - Cisco Webex Messenger is not supported on IPv6.
- **Telephony Limitations**
 - When you upgrade user devices on Cisco Unified Communications Manager to either Two Stacks or IPv6 only, the corresponding Jabber client must be upgraded to 11.6 or later.
 - When an installation includes IPv4 endpoints and IPv6 endpoints, we recommend that you use a hardware MTP to bridge the Audio and Video between these devices. This is supported on hardware MTP with Cisco IOS version 15.5. For example, a Cisco 3945 router must run the following T-train build: c3900e-universalk9-mz.SPA.155-2.T2.bin.
 - At present we do not have a solution roadmap to support IPv4 and IPv6 simultaneously in Cisco endpoints including Jabber. Cisco Unified Communications Manager supports the current functionality which is IPv4-Only and IPv6-Only. An MTP is required to support calls between IPv4-only and IPv6-only endpoints, or IPv4-only or IPv6-only Gateways.
 - Jabber to Jabber calls are not supported on IPv6.
- **File Transfer Limitations**
 - **Advanced File Transfer**—When the client is configured for Two Stacks and Cisco Unified Communications Manager IM and Presence Service is Two Stacks enabled, advanced file transfer is supported on the following Cisco Unified Communications Manager IM and Presence Service versions:
 - 10.5.2 SU2
 - 11.0.1 SU2
 - 11.5
 - **Person to Person file transfer**—For on-premises deployment person to person file transfer between IPv4 and IPv6 clients is not supported. If you have a network configuration with both IPv4 and IPv6 clients, we recommend configuring advanced file transfer.
- **Mobile and Remote Access Limitations**
 - Cisco VCS Expressway for Mobile and Remote Access doesn't support IPv6.

- If Cisco Unified Communications Manager is configured for an IPv6 SIP connection, you can't connect to Cisco Unified Communications Manager using Cisco VCS Expressway for Mobile and Remote Access to use telephony services.

Requirements to Support IPv6 in Android

Android OS Requirement

Android 5.0 and later

Network Requirements

- IPv4 Only mode (Android accepts only IPv4 address)
- Dual Stack with SLAAC (Android accepts both IPv4 and IPv6 address)
- NAT64 or DNS64 (server uses IPv4 address and client uses IPv6 address)

Limitations

- DHCPv6 Limitation
 - DHCPv6 is not supported on an Android device.
- Android OS Limitation
 - Android OS does not support IPv6-only network. For more information on this limitation, see the [Android developer link](#).

Windows

The client uses the ports and protocols listed in the following table. If you plan to deploy a firewall between the client and a server, configure the firewall to allow these ports and protocols.

	Port	Application Layer Protocol	Transport Layer Protocol	Description
Configuration				

	Port	Application Layer Protocol	Transport Layer Protocol	Description
	6970	HTTP	TCP	Connect to the TFTP server to download client configuration files.
	6972	HTTPS	TCP	Connects to the TFTP server to download client configuration files securely for Cisco Unified Communications Manager release 11.0 and later.
	53	DNS	UDP	Hostname resolution.
	3804	CAPF	TCP	Issues Locally Significant Certificates (LSC) to IP phones. This port is the listening port for Cisco Unified Communications Manager Certificate Authority Proxy Function (CAPF) enrollment.
	8443	HTTPS		Traffic to Cisco Unified Communications Manager and Cisco Unified Communications Manager IM and Presence Service.
	8191	SOAP	TCP	Connects to local port to provide Simple Object Access Protocol (SOAP) web services.
Directory Integration —For LDAP contact resolution one of the following ports are used based on LDAP configuration.				
	389	LDAP	TCP	LDAP TCP (UDP) Connects to an LDAP directory service.
	3268	LDAP	TCP	Connects to a Global Catalog server for contact searches.
	636	LDAPS	TCP	LDAPS TCP Connects securely to an LDAP directory service.
	3269	LDAPS	TCP	LDAPS TCP Connects securely to the Global Catalog server.
Instant Messaging and Presence				
	443	XMPP	TCP	XMPP traffic to the Webex Messenger service. The client sends XMPP through this port in cloud-based deployments only. If port 443 is blocked, the client falls back to port 5222.
	5222	XMPP	TCP	Connects to Cisco Unified Communications Manager IM and Presence Service for instant messaging and presence.
	37200	SOCKS5 Bytestream	TCP	Peer to Peer file transfer, In on-premises deployments, the client also uses this port to send screen captures.
	7336	HTTPS	TCP	MFT File transfer (On-Premises only).
Communication Manager Signaling				

	Port	Application Layer Protocol	Transport Layer Protocol	Description
	2748	CTI	TCP	Computer Telephony Interface (CTI) used for desk phone control.
	5060	SIP	TCP	Provides Session Initiation Protocol (SIP) call signaling.
	5061	SIP over TLS	TCP	SIP over TCP Provides secure SIP call signaling. (Used if Secure SIP is enabled for device.)
	30000 to 39999	FECC	UDP	Far end camera control (FECC).
	5070 to 6070	BFCP	UDP	Binary Floor Control Protocol (BFCP) for video screen sharing capabilities.
Voice or Video Media Exchange				
	16384 to 32766	RTP/SRTP	UDP	Cisco Unified Communications Manager media port range used for audio, video, and BFCP video desktop share.
	33434 to 33598	RTP/SRTP	UDP	Cisco Hybrid Services (Jabber to Jabber calling) media port range used for audio and video.
	49152 to 65535	RDP	TCP	IM-only desktop share. Applies to Cisco Jabber for Windows only.
	8000	RTP/SRTP	TCP	Used by Jabber Desk Phone Video Interface, allows users to receive video transmitted to their desk phone devices on their computers through the client.
Unity Connection				
	7080	HTTP	TCP	Used for Cisco Unity Connection to receive notifications of voice messages (new message, message update, and message deleted).
	7443	HTTPS	TCP	Used for Cisco Unity Connection to securely receive notifications of voice messages (new message, message update, and message deleted).
	443	HTTPS	TCP	Connects to Cisco Unity Connection for voicemail.
Cisco Webex Meetings				
	80	HTTP	TCP	Connects to Cisco Webex Meetings Center for meetings.
	443	HTTPS	TCP	Connects to Cisco Webex Meetings Center for meetings.
	8443	HTTPS	TCP	Web access to Cisco Unified Communications Manager and includes connections for the following: <ul style="list-style-type: none"> • Cisco Unified Communications Manager IP Phone (CCMCIP) server for assigned devices. • User Data Service (UDS) for contact resolution.

	Port	Application Layer Protocol	Transport Layer Protocol	Description
Accessories Manager				
	8001		TCP	In Cisco Jabber for Windows and Mac, Sennheiser plugin uses this port for Localhost traffic for call controls.

Ports for Other Services and Protocols

In addition to the ports listed in this section, review the required ports for all protocols and services in your deployment. You can find the port and protocol requirements for different servers in the following documents:

- For Cisco Unified Communications Manager, Cisco Unified Communications Manager IM and Presence Service, see the *TCP and UDP Port Usage Guide*.
- For Cisco Unity Connection, see the *System Administration Guide*.
- For Cisco Webex Meetings Server, see the *Administration Guide*.
- For Cisco Webex services, see the *Administrator's Guide*.
- For Expressway for Mobile and Remote Access, refer to *Cisco Expressway IP Port Usage for Firewall Traversal*.
- For file transfer port usage, see the *Configuration and Administration of IM and Presence Service on Cisco Unified Communications Manager*.

Supported Codecs

Type	Codec	Codec Type	Cisco Jabber for Android	Cisco Jabber for iPhone and iPad	Cisco Jabber for Mac	Cisco Jabber for Windows
Audio	G.711	A-law	Yes Supports normal mode.		Yes	Yes
		μ-law/Mu-law	Yes Supports normal mode.		Yes	Yes
	G.722		Yes		Yes	Yes
	G.722.1	24 kb/s and 32 kb/s	Yes Supports normal mode.		Yes	Yes
	G.729		Does not support Visual Voicemail with G.729; however, you can access voice messages using G.729 and the Call Voicemail feature.		No	No
	G.729a		Yes Minimum requirement for low-bandwidth availability. Only codec that supports low-bandwidth mode. Supports normal mode.		Yes	Yes
	Opus		Yes		Yes	Yes
Video	H.264/AVC		Yes		Yes	Yes
Voicemail	G.711	A-law	Yes		Yes	No
		μ-law / Mu-law (default)	Yes		Yes	No
	GSM 06.10		Yes		Yes	No
	PCM linear		Yes		Yes	No

If users have issues with voice quality when using Cisco Jabber for Android or Cisco Jabber for iPhone and iPad, they can turn low-bandwidth mode on and off in the client settings.

Virtual Environment Requirements

Software Requirements

To deploy Cisco Jabber for Windows in a virtual environment, select from the following supported software versions:

Software	Supported Versions
Citrix XenDesktop	7.6, 7.5, 7.1
Citrix XenApp	7.6, published desktop 7.5, published desktop 6.5, published desktop
VMware Horizon View	6.1, 6.0, 5.3

Softphone Requirements

For softphone calls, use Cisco Virtualization Experience Media Engine (VXME).

Audio and Video Performance Reference



Attention

The following data is based on testing in a lab environment. This data is intended to provide an idea of what you can expect in terms of bandwidth usage. The content in this topic is not intended to be exhaustive or to reflect all media scenarios that might affect bandwidth usage.

Audio Bit Rates for Cisco Jabber Desktop Clients

The following audio bit rates apply to Cisco Jabber for Windows and Cisco Jabber for Mac.

Codec	RTP (kbits/second)	Actual bit rate (kbits/second)	Notes
G.722.1	24/32	54/62	High quality compressed
G.711	64	80	Standard uncompressed
G.729a	8	38	Low quality compressed

Audio Bit Rates for Cisco Jabber Mobile Clients

The following audio bit rates apply to Cisco Jabber for iPad and iPhone and Cisco Jabber for Android.

Codec	Codec bit rate (kbits/second)	Network Bandwidth Utilized (kbits/second)
g.711	64	80
g.722.1	32	48
g.722.1	24	40
g.729a	8	24

Video Bit Rates for Cisco Jabber Desktop Clients

The following video bit rates (with g.711 audio) apply to Cisco Jabber for Windows and Cisco Jabber for Mac. This table does not list all possible resolutions.

Resolution	Pixels	Measured bit rate (kbits per second) with g.711 audio
w144p	256 x 144	156
w288p This is the default size of the video rendering window for Cisco Jabber.	512 x 288	320
w448p	768 x 448	570
w576p	1024 x 576	890
720p	1280 x 720	1300



Note

The measured bit rate is the actual bandwidth used (RTP payload + IP packet overhead).

Video Bit Rates for Cisco Jabber for Android

The client captures and transmits video at 15 fps.

Resolution	Pixels	Bit Rate (kbits per second) with g.711 audio
w144p	256 x 144	290
w288p	512 x 288	340
w360p	640 x 360	415
w720p	1280 x 720	1024

Video	Resolution	Bandwidth
HD	1280 x 720	1024

Video	Resolution	Bandwidth
VGA	640 x 360	512
CIF	488x211	310

**Note**

To send and receive HD video during calls:

- Configure the maximum bit rate for video calls higher than 1024 kbps in Cisco Unified Communications Manager.
- Enable DSCP on a router to transmit video RTP package with high priority.

Android Devices That Support Sending High Definition Videos

Cisco Jabber for Android supports sending high definition video over a video call in these devices:

- Samsung Galaxy S6
- Samsung Galaxy S6 edge
- Samsung Galaxy S6 edge+
- Samsung Galaxy Note5
- Xiaomi 5

Video Bit Rates for Cisco Jabber for iPhone and iPad

The client captures and transmits at 20 fps.

Resolution	Pixels	Bit rate (kbits/second) with g.711 audio
w144p	256 x 144	290
w288p	512 x 288	340
w360p	640 x 360	415
w720p	1280 x 720	1024

Presentation Video Bit Rates

Cisco Jabber captures at 8 fps and transmits at 2 to 8 fps.

The values in this table do not include audio.

Pixels	Estimated wire bit rate at 2 fps (kbits per second)	Estimated wire bit rate at 8 fps (kbits per second)
720 x 480	41	164

Pixels	Estimated wire bit rate at 2 fps (kbits per second)	Estimated wire bit rate at 8 fps (kbits per second)
704 x 576	47	188
1024 x 768	80	320
1280 x 720	91	364
1280 x 800	100	400

Maximum Negotiated Bit Rate

You specify the maximum payload bit rate in Cisco Unified Communications Manager in the **Region Configuration** window. This maximum payload bit rate does not include packet overhead, so the actual bit rate used is higher than the maximum payload bit rate you specify.

The following table describes how Cisco Jabber allocates the maximum payload bit rate:

Audio	Interactive video (Main video)
Cisco Jabber uses the maximum audio bit rate	Cisco Jabber allocates the remaining bit rate as follows: The maximum video call bit rate minus the audio bit rate.

COP Files

Required COP Files for All Clients

- cmterm-cucm-uds-912-5.cop.sgn—Cisco Unified Communications Manager 9.1(2).

Required COP Files for Cisco Jabber for Mobile Clients

This table describes about the COP files that are applicable for all Cisco Unified Communications Manager earlier than 11.5.1.

Cisco Jabber Mobile Clients	COP File
Android tablet	cmterm-jabbertablet-install-151020.k3.cop.sgn
Android phone	cmterm-android-install-151020.k3.cop.sgn
iPhone	cmterm-iphone-install-151020.k3.cop.sgn
iPad	cmterm-jabbertablet-install-151020.k3.cop.sgn



Note

For Cisco Unified Communications Manager later than 11.5.1, you don't have to install COP file separately, because it is installed with the Cisco Unified Communications Manager software.

Bandwidths

Region configuration on Cisco Unified Communications Manager can limit the bandwidth available to the client.

Use regions to limit the bandwidth that is used for audio and video calls within a region and between existing regions by specifying the transport-independent maximum bit rates for audio and for video calls. For more information on region configuration, see the Cisco Unified Communications Manager documentation for your release.

Bandwidth Performance Expectations for Cisco Jabber Desktop Clients

Cisco Jabber for Mac separates the bit rate for audio and then divides the remaining bandwidth equally between interactive video and presentation video. The following table provides information to help you understand what performance you should be able to achieve per bandwidth:

Upload speed	Audio	Audio + Interactive video (Main video)
125 kbps under VPN	At bandwidth threshold for g.711. Sufficient bandwidth for g.729a and g.722.1.	Insufficient bandwidth for video.
384 kbps under VPN	Sufficient bandwidth for any audio codec.	w288p (512 x 288) at 30 fps
384 kbps in an enterprise network	Sufficient bandwidth for any audio codec.	w288p (512 x 288) at 30 fps
1000 kbps	Sufficient bandwidth for any audio codec.	w576p (1024 x 576) at 30 fps
2000 kbps	Sufficient bandwidth for any audio codec.	w720p30 (1280 x 720) at 30 fps

Cisco Jabber for Windows separates the bit rate for audio and then divides the remaining bandwidth equally between interactive video and presentation video. The following table provides information to help you understand what performance you should be able to achieve per bandwidth:

Upload speed	Audio	Audio + Interactive video (Main video)	Audio + Presentation video (Desktop sharing video)	Audio + Interactive video + Presentation video
125 kbps under VPN	At bandwidth threshold for g.711. Sufficient bandwidth for g.729a and g.722.1	Insufficient bandwidth for video.	Insufficient bandwidth for video.	Insufficient bandwidth for video.
384 kbps under VPN	Sufficient bandwidth for any audio codec.	w288p (512 x 288) at 30 fps	1280 x 800 at 2+ fps	w144p (256 x 144) at 30 fps + 1280 x 720 at 2+ fps

Upload speed	Audio	Audio + Interactive video (Main video)	Audio + Presentation video (Desktop sharing video)	Audio + Interactive video + Presentation video
384 kbps in an enterprise network	Sufficient bandwidth for any audio codec.	w288p (512 x 288) at 30 fps	1280 x 800 at 2+ fps	w144p (256 x 144) at 30 fps + 1280 x 800 at 2+ fps
1000 kbps	Sufficient bandwidth for any audio codec.	w576p (1024 x 576) at 30 fps	1280 x 800 at 8 fps	w288p (512 x 288) at 30 fps + 1280 x 800 at 8 fps
2000 kbps	Sufficient bandwidth for any audio codec.	w720p30 (1280 x 720) at 30 fps	1280 x 800 at 8 fps	w288p (1024 x 576) at 30 fps + 1280 x 800 at 8 fps

Note that VPN increases the size of the payload, which increases the bandwidth consumption.

Bandwidth Performance Expectations for Cisco Jabber for Android

Note that VPN increases the size of the payload, which increases the bandwidth consumption.

Upload speed	Audio	Audio + Interactive Video (Main Video)
125 kbps under VPN	At bandwidth threshold for g.711. Insufficient bandwidth for video. Sufficient bandwidth for g.729a and g.722.1.	Insufficient bandwidth for video.
256 kbps	Sufficient bandwidth for any audio codec.	Transmission rate (Tx) — 256 x 144 at 15 fps Reception rate (Rx) — 256 x 144 at 30 fps
384 kbps under VPN	Sufficient bandwidth for any audio codec.	Tx — 640 x 360 at 15 fps Rx — 640 x 360 at 30 fps
384 kbps in an enterprise network	Sufficient bandwidth for any audio codec.	Tx — 640 x 360 at 15 fps Rx — 640 x 360 at 30 fps



Note

Due to device limitations, the Samsung Galaxy SII and Samsung Galaxy SIII devices cannot achieve the maximum resolution listed in this table.

Bandwidth Performance Expectations for Cisco Jabber for iPhone and iPad

The client separates the bit rate for audio and then divides the remaining bandwidth equally between interactive video and presentation video. The following table provides information to help you understand what performance you should be able to achieve per bandwidth.

Note that VPN increases the size of the payload, which increases the bandwidth consumption.

Upload speed	Audio	Audio + Interactive Video (Main Video)
125 kbps under VPN	At bandwidth threshold for g.711. Insufficient bandwidth for video. Sufficient bandwidth for g.729a and g.722.1.	Insufficient bandwidth for video.
290 kbps	Sufficient bandwidth for any audio codec.	256 x 144 at 20 fps
415 kbps	Sufficient bandwidth for any audio codec.	640 x 360 at 20 fps
1024 kbps	Sufficient bandwidth for any audio codec.	1280 x 720 at 20 fps

Video Rate Adaptation

Cisco Jabber uses video rate adaptation to negotiate optimum video quality. Video rate adaptation dynamically increases or decreases video bit rate throughput to handle real-time variations on available IP path bandwidth.

Cisco Jabber users should expect video calls to begin at lower resolution and scale upwards to higher resolution over a short period of time. Cisco Jabber saves history so that subsequent video calls should begin at the optimal resolution.



CHAPTER 3

Deployment Scenarios

- [On-Premises Deployment, on page 33](#)
- [Cloud-Based Deployments, on page 36](#)
- [Deployment in a Virtual Environment, on page 38](#)
- [Remote Access, on page 40](#)
- [Deployment with Single Sign-On, on page 47](#)

On-Premises Deployment

An on-premises deployment is one in which you set up, manage, and maintain all services on your corporate network.

You can deploy Cisco Jabber in the following modes:

- **Full UC**—To deploy full UC mode, enable instant messaging and presence capabilities, provision voicemail and conferencing capabilities, and provision users with devices for audio and video.
- **IM-Only**—To deploy IM-only mode, enable instant messaging and presence capabilities. Do not provision users with devices.
- **Phone-Only Mode**—In Phone-Only mode, the user's primary authentication is to Cisco Unified Communications Manager. To deploy phone-only mode, provision users with devices for audio and video capabilities. You can also provision users with additional services such as voicemail.

The default product mode is one in which the user's primary authentication is to an IM and presence server.

On-Premises Deployment with Cisco Unified Communications Manager IM and Presence Service


The following services are available in an on-premises deployment with Cisco Unified Communications Manager IM and Presence Service:

- **Presence**—Publish availability and subscribe to other users' availability through Cisco Unified Communications Manager IM and Presence Service.
- **IM**—Send and receive IMs through Cisco Unified Communications Manager IM and Presence Service.

- **File Transfers**—Send and receive files and screenshots through Cisco Unified Communications Manager IM and Presence Service.
- **Audio Calls**—Place audio calls through desk phone devices or computers through Cisco Unified Communications Manager.
- **Video**—Place video calls through Cisco Unified Communications Manager.
- **Voicemail**—Send and receive voice messages through Cisco Unity Connection.
- **Conferencing**—Integrate with one of the following:
 - Cisco Webex Meetings Center—Provides hosted meeting capabilities.
 - Cisco Webex Meetings Server—Provides on-premises meeting capabilities.

The following figure shows the architecture of an on-premises deployment with Cisco Unified Communications Manager IM and Presence Service.

Figure 1: On-Premises Deployment with Cisco Unified Communications Manager IM and Presence Service



340058

Computer Telephony Integration

Cisco Jabber for Windows and Cisco Jabber for Mac for Mac support CTI of Cisco Jabber from a third party application.

Computer Telephony Integration (CTI) enables you to use computer-processing functions while making, receiving, and managing telephone calls. A CTI application can allow you to retrieve customer information from a database on the basis of information that caller ID provides and can enable you to use information that an interactive voice response (IVR) system captures.

For more information on CTI, see the CTI sections in the appropriate release of the *Cisco Unified Communications Manager System Guide*. Or you can see the following sites on the Cisco Developer Network for information about creating applications for CTI control through Cisco Unified Communications Manager APIs:

- Cisco TAPI: <https://developer.cisco.com/site/jtapi/overview/>
- Cisco JTAPI: <https://developer.cisco.com/site/jtapi/overview/>

On-Premises Deployment in Phone Mode

The following services are available in a phone mode deployment:


- **Contact**—This is applicable for mobile clients only. Cisco Jabber updates the contact information from the phone's contact address book.
- **Audio Calls**—Place audio calls through desk phone devices or on computers through Cisco Unified Communications Manager.
- **Video**—Place video calls through Cisco Unity Connection.
- **Voicemail**—Send and receive voice messages through Cisco Unity Connection.
- **Conferencing**—Integrate with one of the following:
 - **Cisco Webex Meetings Center**—Provides hosted meeting capabilities.
 - **Cisco Webex Meetings Server**—Provides on-premises meeting capabilities.



Note Cisco Jabber for Android and Cisco Jabber for iPhone and iPad do not support conferencing in phone mode.

The following figure shows the architecture of an on-premises deployment in phone mode.

Figure 2: On-Premises Deployment in Phone Mode



Softphone

Softphone mode downloads the configuration file from the TFTP server and operates as a SIP registered endpoint. The client uses the CCMCIP or UDS service to get the device name to register with Cisco Unified Communications Manager.

Deskphone

Deskphone mode creates a CTI connection with Cisco Unified Communications Manager to control the IP Phone. The client uses CCMCIP to gather the information about devices associated with a user and creates a list of IP phones available for control by the client.

Cisco Jabber for Mac in deskphone mode doesn't support desk phone video.

Extend and Connect

Cisco Unified Communications Manager Extend and Connect capabilities enable users control calls on devices such as public switched telephone network (PSTN) phones and private branch exchange (PBX) devices. For more information, see the Extend and Connect feature for your Cisco Unified Communications Manager release.

We recommend that you use extend and connect capabilities with Cisco Unified Communications Manager 9.1(1) and later.

Cloud-Based Deployments

A cloud-based deployment is one in which Cisco Webex hosts services. You manage and monitor your cloud-based deployment with the Cisco Webex Administration Tool.


Cloud-Based Deployment

The following services are available in a cloud-based deployment:

- **Contact Source**—The Cisco Webex Messenger service provides contact resolution.
- **Presence**—The Cisco Webex Messenger service lets users publish their availability and subscribe to other users' availability.
- **Instant Messaging**—The Cisco Webex Messenger service lets users send and receive instant messages.
- **Conferencing**—Cisco Webex Meetings Center provides hosted meeting capabilities.

The following figure shows the architecture of a cloud-based deployment.

Figure 3: Cloud-Based Deployment



3416255

Hybrid Cloud-Based Deployment


The following services are available in a hybrid cloud-based deployment:

- **Contact Source**—The Cisco Webex Messenger service provides contact resolution.

- **Presence**—The Cisco Webex Messenger service allows users to publish their availability and subscribe to other users' availability.
- **Instant Messaging**—The Cisco Webex Messenger service allows users to send and receive instant messages.
- **Audio**—Place audio calls through desk phone devices or computers through Cisco Unified Communications Manager.
- **Video**—Place video calls through Cisco Unified Communications Manager.
- **Conferencing**—Cisco Webex Meetings Center provides hosted meeting capabilities.
- **Voicemail**—Send and receive voice messages through Cisco Unity Connection.

The following figure shows the architecture of a hybrid cloud-based deployment.

Figure 4: Hybrid Cloud-Based Deployment



Deployment in a Virtual Environment

You can deploy Cisco Jabber for Windows in a virtual environment.

The following features are supported in a virtual environment:

- Instant messaging and presence with other Cisco Jabber clients
- Desk phone control
- Voicemail
- Presence integration with Microsoft Outlook 2007, 2010 and 2013

Virtual Environment and Roaming Profiles

In a virtual environment, users do not always access the same virtual desktop. To guarantee a consistent user experience, these files must be accessible every time that the client is launched. Cisco Jabber stores user data in the following locations:

- `C:\Users\username\AppData\Local\Cisco\Unified Communications\Jabber\CSF`
 - **Contacts**—Contact cache files
 - **History**—Call and chat history
 - **Photo cache**—Caches the directory photos locally
- `C:\Users\username\AppData\Roaming\Cisco\Unified Communications\Jabber\CSF`
 - **Config**—Maintains user configuration files and stores configuration store cache
 - **Credentials**—Stores encrypted username and password file



Note

Cisco Jabber credentials caching is not supported when using Cisco Jabber in non-persistent virtual deployment infrastructure (VDI) mode.

If required, you can exclude files and folders from synchronization by adding them to an exclusion list. To synchronize a subfolder that is in an excluded folder, add the subfolder to an inclusion list.

To preserve personal user settings, you should do the following:

- Do not exclude the following directories:
 - `AppData\Local\Cisco`
 - `AppData\Local\JabberWerxCPP`
 - `AppData\Roaming\Cisco`
 - `AppData\Roaming\JabberWerxCPP`
- Use the following dedicated profile management solutions:
 - **Citrix Profile Management**—Provides a profile solution for Citrix environments. In deployments with random hosted virtual desktop assignments, Citrix profile management synchronizes each user's entire profile between the system it is installed on and the user store.
 - **VMware View Persona Management**—Preserves user profiles and dynamically synchronizes them with a remote profile repository. VMware View Persona Management does not require the configuration of Windows roaming profiles and can bypass Windows Active Directory in the management of VMware Horizon View user profiles. Persona Management enhances the functionality of existing roaming profiles.

Remote Access


Your users may need to access their work from a location that's outside the corporate network. You can provide them access to their work using one of the Cisco products for remote access.

Expressway for Mobile and Remote Access

Expressway for Mobile and Remote Access for Cisco Unified Communications Manager allows users to access their collaboration tools from outside the corporate firewall without using a virtual private network (VPN). Using Cisco collaboration gateways, the client can connect securely to your corporate network from remote locations such as public Wi-Fi networks or mobile data networks.

Figure 5: How the Client Connects to the Expressway for Mobile and Remote Access

The following diagram illustrates the architecture of an Expressway for Mobile and Remote Access



Supported Services

The following table summarizes the services and functionality that are supported when the client uses Expressway for Mobile and Remote Access to remotely connect to Cisco Unified Communications Manager.

Table 3: Summary of Supported Services for Expressway for Mobile and Remote Access

Service	Supported	Unsupported
Directory		
UDS directory search	X	
LDAP directory search		X
Directory photo resolution	X * Using HTTP white list on Cisco Expressway-C	
Intradomain federation	X * Contact search support depends on the format of your contact IDs. For more information, see the note below.	
Interdomain federation	X	

Service	Supported	Unsupported
Instant Messaging and Presence		
On-premises	X	
Cloud	X	
Chat	X	
Group chat	X	
High Availability: On-premises deployments	X	
File transfer: On-premises deployments	X Advanced options available for file transfer using Cisco Unified Communications Manager IM and Presence Service 10.5(2) or later, see the note below.	
File transfer: Cloud deployments	X	
Video screen share - BFCP	X (Cisco Jabber for mobile clients only support BFCP receive.)	
IM-Only Screen Share		x
Audio and Video		
Audio and video calls	X * Cisco Unified Communications Manager 9.1(2) and later	
Deskphone control mode (CTI) (desktop clients only)		X
Extend and connect (desktop clients only)		X
Remote desktop control (desktop clients only)		X
Silent Monitoring and Call Recording		X
Dial via Office - Reverse (mobile clients only)	X	
Session persistency		X
Early media		X
Self Care Portal access		X

Service	Supported	Unsupported
Graceful Registration	X * Applies to Cisco Jabber for Android. Jabber for Android supports graceful registration over Expressway for Mobile and Remote Access from Cisco Unified Communications Manager Release 10.5.(2) 10000-1.	
Voicemail		
Visual voicemail	X * Using HTTP white list on Cisco Expressway-C	
Cisco Webex Meetings		
On-premises		X
Cloud	X	
Cisco Webex screen share (desktop clients only)	X	
Installation (Desktop clients)		
Installer update	X * Using HTTP white list on Cisco Expressway-C	X Not supported on Cisco Jabber for Mac
Customization		
Custom HTML tabs		X
Enhanced911 Prompt	X * To ensure that the web page renders correctly for all Jabber clients operating outside the corporate network, the web page must be a static HTML page because the scripts and link tags are not supported by the E911NotificationURL parameter. For more information, see the latest <i>Parameter Reference Guide for Cisco Jabber</i> .	
Security		
End-to-end encryption	X	

Service	Supported	Unsupported
CAPF enrollment		X
Single Sign-On	X	
Advanced Encryption Standard (AES) 256 and TLS1.2	X * Applies to Cisco Jabber for Android. Advanced encryption is supported only on corporate Wi-Fi	
Troubleshooting (Desktop clients only)		
Problem report generation	X	
Problem report upload		X
High Availability (failover)		
Audio and Video services		X
Voicemail services		X
IM and Presence services	X	

Directory

When the client connects to services using Expressway for Mobile and Remote Access, it supports directory integration with the following limitations.

- **LDAP contact resolution** — The client cannot use LDAP for contact resolution when outside of the corporate firewall. Instead, the client must use UDS for contact resolution.

When users are inside the corporate firewall, the client can use either UDS or LDAP for contact resolution. If you deploy LDAP within the corporate firewall, Cisco recommends that you synchronize your LDAP directory server with Cisco Unified Communications Manager to allow the client to connect with UDS when users are outside the corporate firewall.
- **Directory photo resolution** — To ensure that the client can download contact photos, you must add the server on which you host contact photos to the white list of your Cisco Expressway-C server. To add a server to Cisco Expressway-C white list, use the **HTTP server allow** setting. For more information, see the relevant Cisco Expressway documentation.
- **Intradomain federation** — When you deploy intradomain federation and the client connects with Expressway for Mobile and Remote Access from outside the firewall, contact search is supported only when the contact ID uses one of the following formats:
 - sAMAccountName@domain
 - UserPrincipalName (UPN)@domain
 - EmailAddress@domain
 - employeeNumber@domain

- `telephoneNumber@domain`
- Interdomain federation using XMPP — Expressway for Mobile and Remote Access doesn't enable XMPP Interdomain federation itself. Cisco Jabber clients connecting over Expressway for Mobile and Remote Access can use XMPP Interdomain federation if it has been enabled on Cisco Unified Communications Manager IM and Presence.

Instant Messaging and Presence

When the client connects to services using Expressway for Mobile and Remote Access, it supports instant messaging and presence with the following limitations:

File transfer has the following limitations for desktop and mobile clients:

- For Cisco Webex cloud deployments, file transfer is supported.
- For on-premises deployments with Cisco Unified Communication IM and Presence Service 10.5(2) or later, the **Managed File Transfer** selection is supported, however the **Peer-to-Peer** option is not supported.
- For on-premises deployments with Cisco Unified Communications Manager IM and Presence Service 10.0(1) or earlier deployments, file transfer is not supported.
- For Expressway for Mobile and Remote Access deployments with unrestricted Cisco Unified Communications Manager IM and Presence Server, Managed File Transfer is not supported.

Audio and Video Calling

When the client connects to services using Expressway for Mobile and Remote Access, it supports voice and video calling with the following limitations.

- Cisco Unified Communications Manager — Expressway for Mobile and Remote Access supports video and voice calling with Cisco Unified Communications Manager Version 9.1.2 and later.
- Deskphone control mode (CTI) (Desktop clients only) — The client does not support deskphone control mode (CTI), including extension mobility.
- Extend and connect (Desktop clients only) — The client cannot be used to:
 - Make and receive calls on a Cisco IP Phone in the office.
 - Perform mid-call control such as hold and resume on a home phone, hotel phone, or Cisco IP Phone in the office.
- Session Persistency — The client cannot recover from audio and video calls drop when a network transition occurs. For example, if a users start a Cisco Jabber call inside their office and then they walk outside their building and lose Wi-Fi connectivity, the call drops as the client switches to use Expressway for Mobile and Remote Access.
- Early Media — Early Media allows the client to exchange data between endpoints before a connection is established. For example, if a user makes a call to a party that is not part of the same organization, and the other party declines or does not answer the call, Early Media ensures that the user hears the busy tone or is sent to voicemail.

When using Expressway for Mobile and Remote Access, the user does not hear a busy tone if the other party declines or does not answer the call. Instead, the user hears approximately one minute of silence before the call is terminated.

- Self care portal access (Desktop clients only) — Users cannot access the Cisco Unified Communications Manager Self Care Portal when outside the firewall. The Cisco Unified Communications Manager user page cannot be accessed externally.

Cisco Expressway-E proxies all communications between the client and unified communications services inside the firewall. However, the Cisco Expressway-E does not proxy services that are accessed from a browser that is not part of the Cisco Jabber application.

Voicemail

Voicemail service is supported when the client connects to services using Expressway for Mobile and Remote Access.



Note

To ensure that the client can access voicemail services, you must add the voicemail server to the white list of your Cisco Expressway-C server. To add a server to Cisco Expressway-C white list, use the **HTTP server allow** setting. For more information, see the relevant Cisco Expressway documentation.

Cisco Webex Meetings

When the client connects to services using Expressway for Mobile and Remote Access, it supports only cloud-based conferencing using Cisco Webex Meetings Center. The client cannot access the Cisco Webex Meetings Server or join or start on-premises Cisco Webex Meetings.

When users use the Cisco Webex Meetings Servers for meetings or the meeting siteType is ORION, the client cannot access the Cisco Webex Meetings Server, and join or start on-premises Cisco Webex Meetings over Mobile and Remote Access (MRA).

To use the Webex Meetings option in Cisco Jabber for Android, ensure that the meeting client is installed before installing Cisco Jabber for Android.

Installation

Cisco Jabber for Mac — When the client connects to services using Expressway for Mobile and Remote Access, it doesn't support installer updates.

Cisco Jabber for Windows — When the client connects to services using Expressway for Mobile and Remote Access, it supports installer updates.



Note

To ensure that the client can download installer updates, you must add the server that hosts the installer updates to the white list of your Cisco Expressway-C server. To add a server to the Cisco Expressway-C white list, use the **HTTP server allow** setting. For more information, see the relevant Cisco Expressway documentation.

Security

When the client connects to services using Expressway for Mobile and Remote Access, it supports most security features with the following limitations.

- Initial CAPF enrollment — Certificate Authority Proxy Function (CAPF) enrollment is a security service that runs on the Cisco Unified Communications Manager Publisher that issues certificates to Cisco Jabber

(or other clients). To successfully enrol for CAPF, the client must connect from inside the firewall or using VPN.

- **End-to-end encryption** — When users connect through Expressway for Mobile and Remote Access and participate in a call:
 - Media is always encrypted on the call path between the Cisco Expressway-C and devices that are registered to the Cisco Unified Communications Manager using Expressway for Mobile and Remote Access.
 - Media is not encrypted on the call path between the Cisco Expressway-C and devices that are registered locally to Cisco Unified Communications Manager, if either Cisco Jabber or an internal device is not configured with Encrypted security mode.
 - Media is encrypted on the call path between the Expressway-C and devices that are registered locally to Cisco Unified Communication Manager, if both Cisco Jabber and internal device are configured with Encrypted security mode.
 - In case where Cisco Jabber clients always connects through Expressway for Mobile and Remote access, CAPF enrollment is not required to achieve end-to-end encryption. However, Cisco Jabber devices must still be configured with encrypted security mode, and Cisco Unified Communications Manager must be enabled to support mixed mode.
- **Single Sign-On (SSO)** — If you have SSO enabled for your on-premises deployment, it also applies to your Expressway for Mobile and Remote access deployment. If you disable SSO, it is disabled for both on-premises and Expressway for Mobile and Remote access deployments.

Troubleshooting

Cisco Jabber for Windows only. Problem report upload — When the desktop client connects to services using Expressway for Mobile and Remote Access, it cannot send problem reports because the client uploads problem reports over HTTPS to a specified internal server.

To work around this issue, users can save the report locally and send the report in another manner.

High Availability (failover)

High Availability means that if the client fails to connect to the primary server, it fails over to a secondary server with little or no interruption to the service. In relation to high availability being supported on the Expressway for Mobile and Remote Access, high availability refers to the server for the specific service failing over to a secondary server (such as Instant Messaging and Presence).

Some services are available on the Expressway for Mobile and Remote Access that are not supported for high availability. This means that if users are connected to the client from outside the corporate network and the instant messaging and presence server fails over, the services will continue to work as normal. However, if the audio and video server or voicemail server fails over, those services will not work as the relevant servers do not support high availability.

Cisco AnyConnect Deployments

Cisco AnyConnect refers to a server-client infrastructure that enables the client to connect securely to your corporate network from remote locations such as Wi-Fi networks or mobile data networks.

The Cisco AnyConnect environment includes the following components:

- Cisco Adaptive Security Appliance — Provides a service to secure remote access.
- Cisco AnyConnect Secure Mobility Client — Establishes a secure connection to Cisco Adaptive Security Appliance from the user's device.

This section provides information that you should consider when deploying the Cisco Adaptive Security Appliance (ASA) with the Cisco AnyConnect Secure Mobility Client. Cisco AnyConnect is the supported VPN for Cisco Jabber for Android and Cisco Jabber for iPhone and iPad. If you use an unsupported VPN client, ensure that you install and configure the VPN client using the relevant third-party documentation.

For Samsung devices running Android OS 4.4.x, use Samsung AnyConnect version 4.0.01128 or later. For Android OS version above 5.0, you must use Cisco AnyConnect software version later than 4.0.01287.

Cisco AnyConnect provides remote users with secure IPsec (IKEv2) or SSL VPN connections to the Cisco 5500 Series ASA. Cisco AnyConnect can be deployed to remote users from the ASA or using enterprise software deployment systems. When deployed from the ASA, remote users make an initial SSL connection to the ASA by entering the IP address or DNS name in the browser of an ASA configured to accept clientless SSL VPN connections. The ASA then presents a login screen in the browser window, if the user satisfies the login and authentication, it downloads the client that matches the computer operating system. After downloading, the client installs and configures itself and establishes an IPsec (IKEv2) or SSL connection to the ASA.

For information about requirements for Cisco Adaptive Security Appliance and Cisco AnyConnect Secure Mobility Client, see the *Software Requirements* topic.

Related Topics

[Navigating the Cisco ASA Series Documentation](#)

[Cisco AnyConnect Secure Mobility Client](#)

Deployment with Single Sign-On

You can enable your services with Security Assertion Markup Language (SAML) single sign-on (SSO). SAML SSO can be used in on-premises, cloud, or hybrid deployments.

The following steps describe the sign-in flow for SAML SSO after your users start their Cisco Jabber client:

1. The user starts the Cisco Jabber client. If you configure your Identity Provider (IdP) to prompt your users to sign in using a web form, the form is displayed within the client.
2. The Cisco Jabber client sends an authorization request to the service that it is connecting to, such as Cisco Webex Messenger service, Cisco Unified Communications Manager, or Cisco Unity Connection.
3. The service redirects the client to request authentication from the IdP.
4. The IdP requests credentials. Credentials can be supplied in one of the following methods:
 - Form-based authentication that contains username and password fields.
 - Kerberos for Integrated Windows Authentication (IWA) (Windows only)
 - Smart card authentication (Windows only)
 - Basic HTTP authentication method in which client offers the username and password when making an HTTP request.
5. The IdP provides a cookie to the browser or other authentication method. The IdP authenticates the identity using SAML, which allows the service to provide the client with a token.
6. The client uses the token for authentication to log in to the service.

Authentication Methods

The authentication mechanism impacts how a user signs on. For example, if you use Kerberos, the client does not prompt users for credentials, because your users already provided authentication to gain access to the desktop.

User Sessions

Users sign in for a *session*, which gives them a predefined period to use Cisco Jabber services. To control how long sessions last, you configure cookie and token timeout parameters.

Configure the IdP timeout parameters with an appropriate amount of time to ensure that users are not prompted to log in. For example, when Jabber users switch to an external Wi-Fi, are roaming, their laptops hibernate, or their laptop goes to sleep due to user inactivity. Users will not have to log in after resuming the connection, provided the IdP session is still active.

When a session has expired and Jabber is not able to silently renew it, because user input is required, the user is prompted to reauthenticate. This can occur when the authorization cookie is no longer valid.

If Kerberos or a Smart card is used, no action is needed to reauthenticate, unless a PIN is required for the Smart card; there is no risk of interruption to services, such as voicemail, incoming calls, or instant messaging.

Single Sign-On Requirements

SAML 2.0

You must use SAML 2.0 to enable single sign-on (SSO) for Cisco Jabber clients using Cisco Unified Communications Manager services. SAML 2.0 is not compatible with SAML 1.1. You must select an IdP that uses the SAML 2.0 standard. The supported identity providers have been tested to be compliant with SAML 2.0 and can be used to implement SSO.

Supported Identity Providers

The IdP must be Security Assertion Markup Language (SAML) compliant. The clients support the following identity providers:

- Ping Federate 6.10.0.4
- Microsoft Active Directory Federation Services (ADFS) 2.0
- Open Access Manager (OpenAM) 10.1

**Note**

Ensure that you configure Globally Persistent cookies for use with OpenAM.

When you configure the IdP, the configured settings impact how you sign into the client. Some parameters, such as the type of cookie (persistent or session), or the authentication mechanism (Kerberos or Web form), determine how often you have to be authenticated.

Cookies

To enable cookie sharing with the browser, you must use persistent cookies and not session cookies. Persistent cookies prompt the user to enter credentials one time in the client or in any other desktop application that uses Internet Explorer. Session cookies require that users enter their credentials every time the client is launched.

You configure persistent cookies as a setting on the IdP. If you are using Open Access Manager as your IdP, you must configure Globally Persistent cookies (and not Realm Specific Persistent Cookies).

When a user has successfully signed in to Cisco Jabber for iPhone and iPad using SSO credentials, cookies are saved in the iOS keychain by default. If cookies are in the iOS keychain, users don't need to enter sign in credentials for the next sign in, unless the cookie expires during sign in. Cookies are deleted from iOS keychain in the following scenarios:

- Manually sign out of Cisco Jabber
- Cisco Jabber is reset
- After rebooting the iOS device
- Cisco Jabber is closed manually

If the the iOS system stops Cisco Jabber for iPhone and iPad in the background, Cisco Jabber allows users to automatically sign in without entering password.

Required Browsers

To share the authentication cookie (issued by IdP) between the browser and the client, you must specify one of the following browsers as your default browser:

Product	Required Browser
Cisco Jabber for Windows	Internet Explorer
Cisco Jabber for Mac	Safari
Cisco Jabber for iPhone and iPad	Safari
Cisco Jabber for Android	Chrome or Internet Explorer



Note An embedded browser cannot share a cookie with an external browser when using SSO with Cisco Jabber for Android.

Single Sign-On and Remote Access

For users that provide their credentials from outside the corporate firewall using Expressway Mobile and Remote Access, single sign-on has the following restrictions:

- Single sign-on (SSO) is available with Cisco Expressway 8.5 and Cisco Unified Communications Manager release 10.5.2 or later.
- The Identity Provider used must have the same internal and external URL. If the URL is different, the user may be prompted to sign in again when changing from inside to outside the corporate firewall and vice versa.



CHAPTER 4

User Management

- [Jabber IDs, on page 51](#)
- [IM Address Scheme, on page 52](#)
- [Service Discovery using Jabber IDs, on page 52](#)
- [SIP URI, on page 53](#)
- [LDAP User ID, on page 53](#)
- [User ID Planning for Federation, on page 53](#)
- [Proxy Addresses for User Contact Photos, on page 53](#)
- [Authentication and Authorization, on page 53](#)
- [Multiple Resource Login, on page 54](#)

Jabber IDs

Cisco Jabber uses a Jabber ID to identify the contact information in the contact source.

The default Jabber ID is created using the user ID and the presence domain.

For example, Adam McKenzie has a user ID of `amckenzie`, his domain is `example.com` and his Jabber ID is `amckenzie@example.com`.

The following characters are supported in a Cisco Jabber user ID or email address:

- Uppercase characters (A to Z)
- Lowercase characters (a to z)
- Numbers (0-9)
- Period (.)
- Hyphen (-)
- Underscore (_)
- Tilde (~)

When populating the contact list the client will search the contact source using the Jabber IDs to resolve the contacts and display the firstname, lastname, and any other contact information.

IM Address Scheme

Cisco Jabber 10.6 and later supports multiple presence domain architecture models for on premises deployments when the domains are on the same presence architecture, for example users in example-us.com and example-uk.com. Cisco Jabber supports flexible IM Address Scheme using Cisco Unified Communications Manager IM and Presence 10.x or later. The IM Address scheme is the Jabber ID that identifies the Cisco Jabber users.

To support multi domain models, all components of the deployment require the following versions:

- Cisco Unified Communications IM and Presence server nodes and call control nodes version 10.x or later.
- All clients running on Windows, Mac, IOS and Android version 10.6 or later.

Only deploy Cisco Jabber with multiple domain architecture in the following scenarios:

- Cisco Jabber 10.6 or later is deployed as a new installation to all users in your organization on all platforms (Windows, Mac, IOS and Android, including Android based IP Phones such as the DX series).
- Before making any domain or IM address changes on the presence server, Cisco Jabber is upgraded to version 10.6 or later for all users on all platforms (Windows, Mac, IOS and Android, including Android based IP Phones such as the DX series).

The available IM address schemes in the Advanced Presence Settings are:

- UserID@[Default Domain]
- Directory URI

UserID@[Default Domain]

The User ID field is mapped to an LDAP field. This is the default IM Address Scheme.

For example, user Anita Perez has an account name aperez and the User ID field is mapped to the sAMAccountName LDAP field. The address scheme used is aperez@example.com.

Directory URI

The Directory URI is mapped to the **mail** or **msRTCSIP-primaryuseraddress** LDAP fields. This option provides a scheme that is independent of the user ID for authentication.

For example, user Anita Perez has an account name aperez, the mail field is Anita.Perez@domain.com, the address scheme used is Anita.Perez@domain.com.

Service Discovery using Jabber IDs

Service discovery takes the Jabber ID entered in the format [userid]@[domain.com] and by default, extracts the domain.com portion of the Jabber ID to discover the services available. For a deployment where the presence domain is not the same as the service discovery domain, you can include the service discovery domain information during installation as follows:

- In Cisco Jabber for Windows this is done using the SERVICES_DOMAIN command line argument.

- In Cisco Jabber for Mac, Cisco Jabber for Android, or Cisco Jabber for iPhone and iPad the service discovery domain can be set using the `ServicesDomain` parameter used with URL configuration.

SIP URI

A SIP URI is associated with each user. The SIP URI can be an email address, an IMAddress, or a UPN.

The SIP URI is configured using the Directory URI field in Cisco Unified Communications Manager. These are the available options:

- mail
- msRTCSIP-primaryuseraddress

Users can search for contacts and dial contacts by entering a SIP URI.

LDAP User ID

When you synchronize from your directory source to Cisco Unified Communications Manager, the user ID is populated from an attribute in the directory. The default attribute that holds the user ID is `sAMAccountName`.

User ID Planning for Federation

For federation, Cisco Jabber requires the contact ID or user ID for each user to resolve contacts during contact searches.

In the `jabber-config.xml` file you set the attribute for the user ID in the `SipUri BDISipUri` parameter. The default value is `msRTCSIP-PrimaryUserAddress`. If there is a prefix to remove from your user ID you can set a value in the `UriPrefix BDIUriPrefix` parameter.

Proxy Addresses for User Contact Photos

Cisco Jabber accesses the photo server to retrieve contact photos. If your network configuration contains a Web Proxy, you need to ensure that Cisco Jabber can access the Photo Server.

Authentication and Authorization

Cisco Unified Communications Manager LDAP Authentication

LDAP authentication is configured on Cisco Unified Communications Manager to authenticate with the directory server.

When users sign in to the client, the presence server routes that authentication to Cisco Unified Communications Manager. Cisco Unified Communications Manager then proxies that authentication to the directory server.

Cisco Webex Messenger Login Authentication

Cisco Webex Messenger authentication is configured using the Cisco Webex Administration tool.

When users sign in to the client, the information is sent to the Cisco Webex Messenger and an authentication token is sent back to the client.

Single Sign-On Authentication

Single Sign on authentication is configured using an Identity Provider (IdP) and services.

When users sign in to the client, the information is sent to the IdP and once the credentials are accepted an authentication token is sent back to Cisco Jabber.

Voicemail Authentication

Users need to exist on Cisco Unity Connection. Cisco Unity Connection supports multiple authentication types. If Cisco Unified Communications Manager and Cisco Unity Connection use the same authentication then we recommend that Cisco Jabber is configured to use the same credentials.

Multiple Resource Login

All Cisco Jabber clients register with one of the following central IM and Presence Service nodes when a user logs in to the system. This node tracks availability, contact lists, and other aspects of the IM and Presence Service environment.

- On-Premises Deployments: Cisco Unified Communications Manager IM and Presence Service.
- Cloud Deployments: Cisco Webex.

This IM and Presence Service node tracks all of the registered clients associated with each unique network user in the following order:

1. When a new IM session is initiated between two users, the first incoming message is broadcast to all of the registered clients of the receiving user.
2. The IM and Presence Service node waits for the first response from one of the registered clients.
3. The first client to respond then receives the remainder of the incoming messages until the user starts responding using another registered client.
4. The node then reroutes subsequent messages to this new client.



Note

If there is no active resource when a user is logged into multiple devices, then priority is given to the client with the highest presence priority. If the presence priority is the same on all devices, then priority is given to the latest client the user logged in to.



CHAPTER 5

Service Discovery

- [How the Client Connects to Services, on page 55](#)
- [How the Client Locates Services, on page 59](#)
- [Method 1: Search For Services, on page 60](#)
- [Method 2: Customization, on page 72](#)
- [Method 3: Manual Installations, on page 73](#)
- [High Availability, on page 74](#)
- [Survivable Remote Site Telephony, on page 76](#)
- [Configuration Priorities, on page 76](#)
- [Group Configurations Using Cisco Support Field, on page 77](#)

How the Client Connects to Services

To connect to services, Cisco Jabber requires the following information:

- Source of authentication that enables users to sign in to the client.
- Location of services.

You can provide that information to the client with the following methods:

URL Configuration

Users are sent an email from their administrators. The email contains a URL that will configure the domain needed for service discovery.

Service Discovery

The client automatically locates and connects to services.

Manual Connection Settings

Users manually enter connection settings in the client user interface.

Cisco Webex Service Discovery

Cisco Jabber sends a cloud HTTP request to the CAS URL for the Cisco Webex Messenger service. Cisco Jabber authenticates users with Cisco Webex Messenger Service and connects to the available services.

The services are configured on Cisco Webex Administration Tool.

Cisco Intercluster Lookup Service

In an environment with multiple Cisco Unified Communications Manager clusters, you configure Intercluster Lookup Service (ILS). ILS enables the client to find the user's home cluster and discover services.

Expressway for Mobile and Remote Access Service Discovery

Expressway for Mobile and Remote Access enables remote users access services.

The client queries the name server for SRV records. With the `_collab-edge` SRV record the client connects to the internal network through Expressway for Mobile and Remote Access and discover services.

The name server returns the `_collab-edge` SRV record and the client gets the location of the Cisco Expressway-E server. The Cisco Expressway-E server then provides the client with the results of the query to the internal name server. This must include the `_cisco-uds` SRV record, the client then retrieves the service profiles from Cisco Unified Communication Manager

Recommended Connection Methods

The method that you should use to provide the client with the information it needs to connect to services depends on your deployment type, server versions, and product modes. The following tables highlight various deployment methods and how to provide the client with the necessary information.

Table 4: On-Premises Deployments for Cisco Jabber for Windows

Product Mode	Server Versions	Discovery Method	Non DNS SRV Record Method
Full UC (default mode)	Release 9.1.2 and later: <ul style="list-style-type: none"> • Cisco Unified Communications Manager • Cisco Unified Communications Manager IM and Presence Service 	A DNS SRV request against <code>_cisco-uds.<domain></code>	Use the following installer switches and values: <ul style="list-style-type: none"> • AUTHENTICATOR=CUP • CUP_ADDRESS= <presence_server_address>
IM Only (default mode)	Release 9 and later: <ul style="list-style-type: none"> • Cisco Unified Communications Manager IM and Presence Service 	A DNS SRV request against <code>_cisco-uds.<domain></code>	Use the following installer switches and values: <ul style="list-style-type: none"> • AUTHENTICATOR=CUP • CUP_ADDRESS= <presence_server_address>

Product Mode	Server Versions	Discovery Method	Non DNS SRV Record Method
Phone Mode	Release 9 and later: Cisco Unified Communications Manager	A DNS SRV request against <code>_cisco-uds.<domain></code>	Use the following installer switches and values: <ul style="list-style-type: none"> • AUTHENTICATOR=CUCM • TFTP=<CUCM_address> • CCMCIP=<CUCM_address> • PRODUCT_MODE=phone_mode High availability is not supported using this method of deployment.

Cisco Unified Communications Manager release 9.x and earlier—If you enable Cisco Extension Mobility, the `Cisco Extension Mobility` service must be activated on the Cisco Unified Communications Manager nodes that are used for CCMCIP. For information about Cisco Extension Mobility, see the *Feature and Services* guide for your Cisco Unified Communications Manager release.



Note Cisco Jabber release 9.6 and later can still discover full Unified Communications and IM-only services using the `_cuplogin` DNS SRV request but a `_cisco-uds` request will take precedence if it is present.

Use the `SERVICES_DOMAIN` installer switch to specify the value of the domain where DNS records reside if you want users to bypass the email screen during the first login of a fresh installation.



Note The services domain is read from a cached configuration if you are upgrading from Cisco Jabber for Windows 9.2.

Table 5: On-Premises Deployments for Cisco Jabber for Mac

Product Mode	Server Versions	Discovery Method
Full UC (default mode)	Release 9 and later: <ul style="list-style-type: none"> • Cisco Unified Communications Manager • Cisco Unified Communications Manager IM and Presence Service 	A DNS SRV request against <code>_cisco-uds.<domain></code>

Table 6: On-Premises Deployments for Cisco Jabber for Android and Cisco Jabber for iPhone and iPad

Product Mode	Server Versions	Discovery Method
Full UC (default mode)	Release 9 and later: <ul style="list-style-type: none"> • Cisco Unified Communications Manager • Cisco Unified Communications Manager IM and Presence Service 	A DNS SRV request against <code>_cisco-uds.<domain></code> and <code>_cuplogin.<domain></code>
IM Only (default mode)	Release 9 and later: Cisco Unified Communications Manager IM and Presence Service	A DNS SRV request against <code>_cisco-uds.<domain></code> and <code>_cuplogin.<domain></code>
Phone mode	Release 9 and later: Cisco Unified Communications Manager	A DNS SRV request against <code>_cisco-uds.<domain></code>



Note Cisco Unified Communications Manager version 9 and later can still discover full Unified Communications and IM-only services using the `_cuplogin` DNS SRV request but a `_cisco-uds` request will take precedence if it is present.

Table 7: Hybrid Cloud-Based Deployments

Server Versions	Connection Method
Cisco Webex Messenger	HTTPS request against <code>https://loginp.webexconnect.com/cas/FederatedSSO?org=<domain></code>

Table 8: Cloud-Based Deployments

Deployment Type	Connection Method
Enabled for single sign-on (SSO)	Cisco Webex Administration Tool Bootstrap file to set the SSO_ORG_DOMAIN argument.
Not enabled for SSO	Cisco Webex Administration Tool

Sources of Authentication

A source of authentication, or an authenticator, enables users to sign in to the client.

Three possible sources of authentication are as follows:

- Cisco Unified Communications Manager IM and Presence—On-premises deployments in either full UC or IM only.
- Cisco Unified Communications Manager—On-premises deployments in phone mode.

- Cisco Webex Messenger Service—Cloud-based or hybrid cloud-based deployments.

How the Client Locates Services

The following steps describe how the client locates services with SRV records:

1. The client's host computer or device gets a network connection.

When the client's host computer gets a network connection, it also gets the address of a Domain Name System (DNS) name server from the DHCP settings.

2. The user employs one of the following methods to discover the service during the first sign in:

- Manual—The user starts Cisco Jabber and then inputs an email-like address on the welcome screen.
- URL configuration—URL configuration allows users to click on a link to cross-launch Cisco Jabber without manually inputting an email.
- Mobile Configuration Using Enterprise Mobility Management—As an alternative to URL configuration, you can configure Cisco Jabber using Enterprise Mobility Management (EMM) with Android for Work on Cisco Jabber for Android and with Apple Managed App Configuration on Cisco Jabber for iPhone and iPad. You need to configure the same parameters in the EMM console that are used for creating URL configuration link.

To create a URL configuration link, you include the following:

- ServicesDomain—The domain that Cisco Jabber uses for service discovery.
- VoiceServicesDomain—For a hybrid deployment, the domain that Cisco Jabber uses to retrieve the DNS SRV records can be different from the ServicesDomain that is used to discover the Cisco Jabber domain.
- ServiceDiscoveryExcludedServices—In certain deployment scenarios, services can be excluded from the service discovery process. These values can be a combination of the following:
 - WEBEX
 - CUCM



Note

When all three parameters are included, service discovery does not happen and the user is prompted to manually enter connection settings.

Create the link in the following format:

```
ciscojabber://provision?ServicesDomain=<domain_for_service_discover>
&VoiceServicesDomain=<domain_for_voice_services>
&ServiceDiscoveryExcludedServices=<services_to_exclude_from_service_discover>
```

Examples:

- `ciscojabber://provision?servicesdomain=example.com`
- `ciscojabber://provision?servicesdomain=example.com
 &VoiceServicesDomain=VoiceServices.example.com`

- `ciscojabber://provision?servicesdomain=example.com
&ServiceDiscoveryExcludedServices=WEBEX,CUCM`

Provide the link to users using email or a website.


Note

If your organization uses a mail application that supports cross-launching proprietary protocols or custom links, you can provide the link to users using email, otherwise provide the link to users using a website.

3. The client queries the name server for the following SRV records in order of priority:

- `_cisco-uds`
- `_collab-edge`

The client caches the results of the DNS query to load on subsequent launches.


Method 1: Search For Services

We recommend that you use this method for how Cisco Jabber detects what services and features are available to users. Searching for services means that the client uses DNS service (SRV) records to determine which services are available to the client.

How the Client Discovers Available Services

The following figure shows the flow that the client uses to connect to services.

Figure 6: Login Flow for Service Discovery



To discover available services, the client does the following:

1. Checks if the network is inside or outside the firewall and if Expressway for Mobile and Remote Access is deployed. The client sends a query to the name server to get DNS Service (SRV) records.
2. Starts monitoring for network changes.

When Expressway for Mobile and Remote Access is deployed, the client monitors the network to ensure that it can reconnect if the network changes from inside or outside the firewall.

3. Issues an HTTP query to a CAS URL for the Cisco Webex Messenger service.

This query enables the client to determine if the domain is a valid Cisco Webex domain.

When Expressway for Mobile and Remote Access is deployed, the client connects to Cisco Webex Messenger Service and uses Expressway for Mobile and Remote Access to connect to Cisco Unified Communications Manager. When the client launches for the first time the user will see a Phone Services Connection Error and will have to enter their credentials in the client options screen, subsequent launches will use the cached information.

4. Queries the name server to get DNS Service (SRV) records, unless the records exist in the cache from a previous query.

This query enables the client to do the following:

- Determine which services are available.
- Determine if it can connect to the corporate network through Expressway for Mobile and Remote Access.

Client Issues an HTTP Query

In addition to querying the name server for SRV records to locate available services, Cisco Jabber sends an HTTP query to the CAS URL for the Cisco Webex Messenger service. This request enables the client to determine cloud-based deployments and authenticate users to the Cisco Webex Messenger service.

When the client gets a services domain from the user, it appends that domain to the following HTTP query:

```
https://loginp.webexconnect.com/cas/FederatedSSO?org=
```

For example, if the client gets `example.com` as the services domain from the user, it issues the following query:

```
https://loginp.webexconnect.com/cas/FederatedSSO?org=example.com
```

That query returns an XML response that the client uses to determine if the services domain is a valid Cisco Webex domain.

If the client determines the services domain is a valid Cisco Webex domain, it prompts users to enter their Cisco Webex credentials. The client then authenticates to the Cisco Webex Messenger service and retrieves the configuration and UC services that are configured in Cisco Webex Org Admin.

If the client determines the services domain is not a valid Cisco Webex domain, it uses the results of the query to the name server to locate available services.

When the client sends the HTTP request to the CAS URL, it uses configured system proxies.

For more information, see the *Configure Proxy Settings* section in the *Cisco Jabber Deployment and Installation Guide*.

Client Queries the Name Server

When the client queries a name server, it sends separate, simultaneous requests to the name server for SRV records.

The client requests the following SRV records in the following order:

- `_cisco-uds`
- `_collab-edge`


If the name server returns:

- `_cisco-uds`—The client detects it is inside the corporate network and connects to Cisco Unified Communications Manager.
- `_collab-edge`—The client attempts to connect to the internal network through Expressway for Mobile and Remote Access and discover services
- None of the SRV records—The client prompts users to manually enter setup and sign-in details.

Client Connects to Internal Services

The following figure shows how the client connects to internal services:

Figure 7: Client Connecting to Internal Services



When connecting to internal services, the goals are to determine the authenticator, sign users in, and connect to available services.

Three possible authenticators can get users past the sign-in screen, as follows:

- Cisco Webex Messenger service—Cloud-based or hybrid cloud-based deployments.
- Cisco Unified Communications Manager—On-premises deployments in phone mode.

The client connects to any services it discovers, which varies depending on the deployment.

1. If the client discovers that the CAS URL lookup indicates a Cisco Webex user, the client does the following:
 1. Determines that the Cisco Webex Messenger service is the primary source of authentication.
 2. Automatically connects to the Cisco Webex Messenger service.
 3. Prompts the user for credentials.
 4. Retrieves client and service configuration.
2. If the client discovers a `_cisco-uds` SRV record, the client does the following:
 1. Prompts the user for credentials to authenticate with Cisco Unified Communications Manager.

2. Locates the user's home cluster.

Locating the home cluster enables the client to automatically get the user's device list and register with Cisco Unified Communications Manager.



Important

In an environment with multiple Cisco Unified Communications Manager clusters, you must configure the Intercluster Lookup Service (ILS). ILS enables the client to find the user's home cluster.

See the appropriate version of the *Cisco Unified Communications Manager Features and Services Guide* to learn how to configure ILS.

3. Retrieves the service profile.

The service profile provides the client with the authenticator as well as client and UC service configuration.

The client determines the authenticator from the value of the Product type field in the IM and presence profile, as follows:

- Cisco Unified Communications Manager—Cisco Unified Presence or Cisco Unified Communications Manager IM and Presence Service is the authenticator.
- WebEx (IM and Presence)—Cisco Webex Messenger service is the authenticator.



Note

As of this release, the client issues an HTTP query in addition to the query for SRV records. The HTTP query allows the client to determine if it should authenticate to the Cisco Webex Messenger service.

As a result of the HTTP query, the client connects to the Cisco Webex Messenger service in cloud-based deployments. Setting the value of the **Product type** field to WebEx does not effect if the client has already discovered the WebEx service using a CAS lookup.

- Not set—If the service profile does not contain an IM and Presence Service configuration, the authenticator is Cisco Unified Communications Manager.

4. Sign in to the authenticator.


After the client signs in, it can determine the product mode.

Client Connects through Expressway for Mobile and Remote Access

If the name server returns the `_collab-edge` SRV record, the client attempts to connect to internal servers through Expressway for Mobile and Remote Access.

The following figure shows how the client connects to internal services when the client is connected to the network through Expressway for Mobile and Remote Access:

Figure 8: Client Connects through Expressway for Mobile and Remote Access



When the name server returns the `_collab-edge` SRV record, the client gets the location of the Cisco Expressway-E server. The Cisco Expressway-E server then provides the client with the results of the query to the internal name server.



Note

The Cisco Expressway-C server looks up the internal SRV records and provides the records to the Cisco Expressway-E server.


After the client gets the internal SRV records, which must include the `_cisco-uds` SRV record, it retrieves service profiles from Cisco Unified Communications Manager. The service profiles then provide the client with the user's home cluster, the primary source of authentication, and configuration.

Cisco UDS SRV Record

In deployments with Cisco Unified Communications Manager version 9 and later, the client can automatically discover services and configuration with the `_cisco-uds` SRV record.

The following figure shows how the client uses the `_cisco-uds` SRV record.

Figure 9: UDS SRV Record Login Flow



380427

1. The client queries the domain name server for SRV records.
2. The domain name server returns the `_cisco-uds` SRV record.
3. The client locates the user's home cluster.

As a result, the client can retrieve the device configuration for the user and automatically register telephony services.

**Important**

In an environment with multiple Cisco Unified Communications Manager clusters, you can configure the Intercluster Lookup Service (ILS). ILS enables the client to find the user's home cluster and discover services. If you do not configure ILS, you must manually configure remote cluster information, similar to the Extension Mobility Cross Cluster (EMCC) remote cluster setup. For more information on remote cluster configurations, see the *Cisco Unified Communications Manager Features and Services Guide*.

4. The client retrieves the user's service profile.

The user's service profile contains the addresses and settings for UC services and client configuration.

The client also determines the authenticator from the service profile.

5. The client signs the user in to the authenticator.

The following is an example of the `_cisco-uds` SRV record:


```
_cisco-uds._tcp.example.com    SRV service location:
    priority = 6
    weight   = 30
    port     = 8443
    svr hostname = cucm3.example.com
_cisco-uds._tcp.example.com    SRV service location:
    priority = 2
    weight   = 20
    port     = 8443
    svr hostname = cucm2.example.com
_cisco-uds._tcp.example.com    SRV service location:
    priority = 1
    weight   = 5
    port     = 8443
    svr hostname = cucm1.example.com
```

Collaboration Edge SRV Record

Cisco Jabber can attempt to connect to internal servers through Expressway for Mobile and Remote Access to discover services with the following `_collab-edge` SRV record.

The following figure shows how the client uses the `_collab-edge` SRV record.

Figure 10: Collaboration Edge Record Login Flow



1. The client queries the external domain name server for SRV records.
2. The name server returns the `_collab-edge` SRV record and does not return the `_cuplogin` or `_cisco-uds` SRV records.

As a result, Cisco Jabber can locate the Cisco Expressway-E server.

3. The client requests the internal SRV records (through Expressway) from the internal domain name server. These SRV records must include the `_cisco-uds` SRV record.
4. The client obtains the internal SRV records (through Expressway).
As a result, the client can locate the Cisco Unified Communications Manager server.
5. The client requests the service profiles (through Expressway) from Cisco Unified Communications Manager.
6. The client retrieves the service profiles (through Expressway) from Cisco Unified Communications Manager.

The service profile contains the user's home cluster, the primary source of authentication, and the client configuration.

DNS Configuration

How the Client Uses DNS

Cisco Jabber uses domain name servers to do the following:

- Determine whether the client is inside or outside the corporate network.
- Automatically discover on-premises servers inside the corporate network.
- Locate access points for Expressway for Mobile and Remote Access on the public Internet.

**Note**

Android OS limitation: Android OS 4.4.2 and 5.0 using the DNS service can resolve only the domain name, but not the hostname.

For more information, see the [Android developer link](#).

How the Client Finds a Name Server

Cisco Jabber looks for DNS records from:

- Internal name servers inside the corporate network.
- External name servers on the public Internet.

When the client's host computer or device gets a network connection, the host computer or device also gets the address of a DNS name server from the DHCP settings. Depending on the network connection, that name server might be internal or external to the corporate network.

Cisco Jabber queries the name server that the host computer or device gets from the DHCP settings.

How the Client Gets a Services Domain

The services domain is discovered by the client in different ways.

New installation:

- User enters an address in the format `username@example.com` in the client user interface.
- User clicks on a configuration URL that includes the service domain. This option is only available in the following versions of the client:
 - Cisco Jabber for Android release 9.6 or later
 - Cisco Jabber for Mac release 9.6 or later
 - Cisco Jabber for iPhone and iPad release 9.6.1 or later
- The client uses installation switches in bootstrap files. This option is only available in the following version of the client:
 - Cisco Jabber for Windows release 9.6 or later

Existing installation:

- The client uses the cached configuration.
- User manually enters an address in the client user interface.

In hybrid deployments the domain required to discover Cisco Webex domain through Central Authentication Service (CAS) lookup may be different to the domain where the DNS records are deployed. In this scenario you set the `ServicesDomain` to be the domain used to discover Cisco Webex and set the `VoiceServicesDomain` to be the domain where DNS records are deployed. The voice services domain is configured as follows:

- The client uses the `VoiceServicesDomain` parameter in the configuration file. This option is available in clients that support the `jabber-config.xml` file.
- User clicks on a configuration URL that includes the `VoiceServicesDomain`. This option is available in the following clients:
 - Cisco Jabber for Android release 9.6 or later
 - Cisco Jabber for Mac release 9.6 or later
 - Cisco Jabber for iPhone and iPad release 9.6.1 or later
- The client uses the `Voice_Services_Domain` installation switch in the bootstrap files. This option is only available in the following version of the client:
 - Cisco Jabber for Windows release 9.6 or later

After Cisco Jabber gets the services domain, it queries the name server that is configured to the client computer or device.

Domain Name System Designs


Where you deploy DNS service (SRV) records depends on the design of your DNS namespace. Typically there are two DNS designs:

- Separate domain names outside and inside the corporate network.
- Same domain name outside and inside the corporate network.

Separate Domain Design

The following figure shows a separate domain design:

Figure 11: Separate Domain Design



An example of a separate domain design is one where your organization registers the following external domain with an Internet name authority: `example.com`.

Your company also uses an internal domain that is one of the following:

- A subdomain of the external domain, for example, `example.local`.
- A different domain to the external domain, for example, `exampledomain.com`.

Separate domain designs have the following characteristics:

- The internal name server has zones that contain resource records for internal domains. The internal name server is authoritative for the internal domains.
- The internal name server forwards requests to the external name server when a DNS client queries for external domains.
- The external name server has a zone that contains resource records for your organization's external domain. The external name server is authoritative for that domain.
- The external name server can forward requests to other external name servers. However, the external name server cannot forward requests to the internal name server.

Deploy SRV Records in a Separate Domain Structure

In a separate name design there are two domains, an internal domain and an external domain. The client queries for SRV records in the services domain. The internal name server must serve records for the services domain. However in a separate name design, a zone for the services domain might not exist on the internal name server.

If the services domain is not currently served by the internal name server, you can:

- Deploy records within an internal zone for the services domain.
- Deploy records within a pinpoint subdomain zone on the internal name server.

Use an Internal Zone for a Services Domain

If you do not already have a zone for the services domain on the internal name server, you can create one. This method makes the internal name server authoritative for the services domain. Because it is authoritative, the internal name server does not forward queries to any other name server.

This method changes the forwarding relationship for the entire domain and has the potential to disrupt your internal DNS structure. If you cannot create an internal zone for the services domain, you can create a pinpoint subdomain zone on the internal name server.


Same Domain Design

An example of a same domain design is one where your organization registers `example.com` as an external domain with an Internet name authority. Your organization also uses `example.com` as the name of the internal domain.

Single Domain, Split-Brain

The following figure shows a single domain with a split-brain domain design.

Figure 12: Single Domain, Split-Brain




Two DNS zones represent the single domain; one DNS zone in the internal name server and one DNS zone in the external name server.

Both the internal name server and the external name server are authoritative for the single domain but serve different communities of hosts.

- Hosts inside the corporate network access only the internal name server.
- Hosts on the public Internet access only the external name server.
- Hosts that move between the corporate network and the public Internet access different name servers at different times.

Single Domain, Not Split-Brain

The following figure shows a single domain that does not have a split-brain domain design.

Figure 13: Single Domain, Not Split-Brain

In the single domain, not split-brain design, internal and external hosts are served by one set of name servers and can access the same DNS information.

**Important**

This design is not common because it exposes more information about the internal network to potential attackers.

Method 2: Customization

You can customize service discovery by using installation parameters, URL configuration, or Enterprise Mobility Management.

Service Discovery Customization

Custom Installations for Cisco Jabber for Windows

Cisco Jabber for Windows provides an MSI installation package that you can use in the following ways:

- **Use the Command Line**—You can specify arguments in a command line window to set installation properties.
Choose this option if you plan to install multiple instances.
- **Run the MSI Manually**—Run the MSI manually on the file system of the client workstation and then specify connection properties when you start the client.
Choose this option if you plan to install a single instance for testing or evaluation purposes.
- **Create a Custom Installer**—Open the default installation package, specify the required installation properties, and then save a custom installation package.
Choose this option if you plan to distribute an installation package with the same installation properties.
- **Deploy with Group Policy**—Install the client on multiple computers in the same domain.

Installer Switches: Cisco Jabber for Windows

When you install Cisco Jabber, you can specify the authenticator and server addresses. The installer saves these details to a bootstrap file. When users launch the client for the first time, it reads the bootstrap file. The bootstrap file takes priority if service discovery is deployed.

Bootstrap files provide a fallback mechanism for service discovery in situations where service discovery has not been deployed and where you do not want users to manually specify their connection settings.

The client only reads the bootstrap file on the initial launch. After the initial launch, the client caches the server addresses and configuration, and then loads from the cache on subsequent launches.

We recommend that you do not use a bootstrap file, and instead use service discovery, in on-premises deployments with Cisco Unified Communications Manager release 9.x and later.

Custom Installations for Cisco Jabber for Mac, iPhone and iPad, and Android

You can create customized installations of Cisco Jabber for Mac or mobile clients by using URL Configuration. For mobile clients you can also use Enterprise Mobility Management. These custom installations depend on installation parameters that enable services.

URL Configuration

To enable users launch Cisco Jabber without having to manually enter service discovery information, provide a configuration URL link to users to install the client.

Provide the configuration URL link to users by emailing the link to the user directly, or by posting the link to a website.

Mobile Configuration Using Enterprise Mobility Management

Before using Enterprise Mobility Management (EMM), ensure:

- The EMM vendor supports Android for Work or Apple Managed App Configuration.
- Android devices OS is 5.0 or later. and iOS devices have iOS 8.0 or later.

You can configure Cisco Jabber using EMM on Cisco Jabber for Android and Cisco Jabber for iPhone and iPad. For more information on setting up EMM, refer to the instructions for administrators provided by the EMM provider.

If you want Jabber to run only on managed devices, then you can deploy certificate-based authentication, and enroll the client certificate through EMM.

Method 3: Manual Installations

As an advanced option, users can manually connect to services at the sign in screen.

High Availability

High Availability for Instant Messaging and Presence

High availability refers to an environment in which multiple nodes exist in a subcluster to provide failover capabilities for instant messaging and presence services. If one node in a subcluster becomes unavailable, the instant messaging and presence services from that node failover to another node in the subcluster. In this way, high availability ensures reliable continuity of instant messaging and presence services for Cisco Jabber.

When using an LDAP or UDS contact source on Cisco Jabber for Mac and Cisco Jabber for mobile clients, high availability is not supported. High availability is only supported for LDAP (EDI) on Cisco Jabber for Windows.

Cisco Jabber supports high availability with the following servers:

Cisco Unified Communications Manager IM and Presence Service release 9.0 and higher

Use the following Cisco Unified Communications Manager IM and Presence Service documentation for more information about high availability.

Configuration and Administration of IM and Presence Service on Cisco Unified Communications Manager

High Availability Client Login Profiles

Troubleshooting High Availability

Active Calls on Hold During Failover

You cannot place an active call on hold if failover occurs from the primary instance of Cisco Unified Communications Manager to the secondary instance.

High Availability in the Client

Client Behavior During Failover

If high availability is configured on the server, then after the primary server fails over to the secondary server, the client temporarily loses presence states for up to one minute. Configure the re-login parameters to define how long the client waits before attempting to re-login to the server.

Configure Login Parameters

In Cisco Unified Communications Manager IM and Presence Service, you can configure the maximum and minimum number of seconds that Cisco Jabber waits before attempting to re-login to the server. On the server, you specify the re-login parameters in the following fields:

- **Client Re-Login Lower Limit**
- **Client Re-Login Upper Limit**

Client Behavior During a Failover

The following figure shows the client's behavior when the Cisco Unified Communications Manager IM and Presence service during a failover.

```

stateDiagram-v2
    [*] --> SOAPCONNECT_P
    SOAPCONNECT_P --> SOAPCONNECT_P : failed [retryCount < 1]
    SOAPCONNECT_P --> SOAPCONNECT_S : retries_exceeded
    SOAPCONNECT_S --> SOAPCONNECT_S : failed [retryCount < 1]
    SOAPCONNECT_S --> SOAPCONNECT_P : retries_exceeded
    SOAPCONNECT_P --> SOAPCONNECT_WITH_SESSION_P : Connected
    SOAPCONNECT_WITH_SESSION_P --> SOAPCONNECT_WITH_SESSION_P : failed [retryCount < 1]
    SOAPCONNECT_WITH_SESSION_P --> SOAPCONNECT_WITH_SESSION_S : retries_exceeded [Start]
    SOAPCONNECT_WITH_SESSION_S --> SOAPCONNECT_WITH_SESSION_S : failed [retryCount < 1]
    SOAPCONNECT_WITH_SESSION_S --> SOAPCONNECT_WITH_SESSION_P : retries_exceeded
    SOAPCONNECT_WITH_SESSION_P --> SOAPCONNECTED : data_received
    SOAPCONNECT_WITH_SESSION_S --> SOAPCONNECTED : data_received
    SOAPCONNECTED --> SOAPCONNECTED : data_received
    SOAPCONNECTED --> SOAPCONNECT_P : retries_exceeded [Start]
    SOAPCONNECTED --> SOAPCONNECT_S : retries_exceeded [Start]
    SOAPCONNECTED --> SOAPCONNECT_WITH_SESSION_P : retries_exceeded [Start]
    SOAPCONNECTED --> SOAPCONNECT_WITH_SESSION_S : retries_exceeded [Start]
    SOAPCONNECTED --> SOAPCONNECTED : failed [retryCount < 1]
    SOAPCONNECTED --> SOAPCONNECT_P : failed [retryCount < 1]
    SOAPCONNECTED --> SOAPCONNECT_S : failed [retryCount < 1]
    SOAPCONNECTED --> SOAPCONNECT_WITH_SESSION_P : failed [retryCount < 1]
    SOAPCONNECTED --> SOAPCONNECT_WITH_SESSION_S : failed [retryCount < 1]
    SOAPCONNECT_P --> XMPPCONNECT_P : Connected
    XMPPCONNECT_P --> XMPPCONNECT_P : failed [retryCount < 1]
    XMPPCONNECT_P --> XMPPCONNECT_S : retries_exceeded [Start]
    XMPPCONNECT_S --> XMPPCONNECT_S : failed [retryCount < 1]
    XMPPCONNECT_S --> XMPPCONNECT_P : retries_exceeded
    XMPPCONNECT_P --> XMPPCONNECTED : Connected
    XMPPCONNECT_S --> XMPPCONNECTED : Connected
    XMPPCONNECTED --> XMPPCONNECTED : data_received
    XMPPCONNECTED --> SOAPCONNECT_P : retries_exceeded [Start]
    XMPPCONNECTED --> SOAPCONNECT_S : retries_exceeded [Start]
    XMPPCONNECTED --> SOAPCONNECT_WITH_SESSION_P : retries_exceeded [Start]
    XMPPCONNECTED --> SOAPCONNECT_WITH_SESSION_S : retries_exceeded [Start]
    XMPPCONNECTED --> XMPPCONNECTED : failed [retryCount < 1]
    XMPPCONNECTED --> SOAPCONNECT_P : failed [retryCount < 1]
    XMPPCONNECTED --> SOAPCONNECT_S : failed [retryCount < 1]
    XMPPCONNECTED --> SOAPCONNECT_WITH_SESSION_P : failed [retryCount < 1]
    XMPPCONNECTED --> SOAPCONNECT_WITH_SESSION_S : failed [retryCount < 1]
    SOAPCONNECT_P --> FAILOVER : Start
    SOAPCONNECT_S --> FAILOVER : Start
    SOAPCONNECT_WITH_SESSION_P --> FAILOVER : Start
    SOAPCONNECT_WITH_SESSION_S --> FAILOVER : Start
    SOAPCONNECTED --> FAILOVER : retries_exceeded [Start]
    SOAPCONNECTED --> FAILOVER : disconnected [sessionLogin]
    XMPPCONNECT_P --> FAILOVER : retries_exceeded [Start]
    XMPPCONNECT_S --> FAILOVER : retries_exceeded [Start]
    XMPPCONNECTED --> FAILOVER : retries_exceeded [Start]
    FAILOVER --> SOAPCONNECT_P : Start
    FAILOVER --> SOAPCONNECT_S : Start
    FAILOVER --> SOAPCONNECT_WITH_SESSION_P : Start
    FAILOVER --> SOAPCONNECT_WITH_SESSION_S : Start
    FAILOVER --> SOAPCONNECTED : Start
    FAILOVER --> XMPPCONNECT_P : Start
    FAILOVER --> XMPPCONNECT_S : Start
    FAILOVER --> XMPPCONNECTED : Start
  
```

- 373352

High Availability for Voice and Video

If one node in a subcluster becomes unavailable, voice and video failover to another node in the subcluster.

By default, it takes up to 120 seconds for a software phone device or desk phone to register with another node. If this timeout period is too long, adjust the value of the SIP Station KeepAlive Interval service parameter for your node. The SIP Station KeepAlive Interval service parameter modifies all phone devices on Cisco Unified Communications Manager. Before you adjust the interval, analyze the impact on the Cisco Unified Communications Manager servers.

To configure service parameters for the node, in Cisco Unified Communications Manager Administration, select **System > Service Parameters**.

For a phone mode deployment using the non-DNS SRV record method, failover isn't possible for Voice and Video, as there is only one Cisco Unified Communications Manager node specified.

Survivable Remote Site Telephony

When the Cisco Unified Communications Manager application is unreachable or the WAN is down, use Cisco Unified Survivable Remote Site Telephony (SRST) to retain basic telephony services for your remote users. When connectivity is lost, the client fails over to the local router at the remote site.



Note

SRST versions 8.5 and 8.6 are supported.

SRST provides basic call control, when a system is in failover only start, end, hold, resume, mute, unmute, and dual-tone multifrequency signaling [DTMF]) are enabled.

The following services are not available during failover:

- Video
- Mid-call features (transfer, iDivert, call park, conferencing, send to mobile)
- Dial via Office (DvO)
- Ad hoc conferencing
- Binary Floor Control Protocol (BFCP) sharing

For detailed instructions about configuring SRST, see the relevant release of the *Cisco Unified Communication Manager Administration Guide*.

Configuration Priorities

When both a service profile and a configuration file are present, the following table describes which parameter value takes precedence.


Service Profile	Configuration File	Which Parameter Value Takes Precedence?
Parameter value is set	Parameter value is set	Service profile

Service Profile	Configuration File	Which Parameter Value Takes Precedence?
Parameter value is set	Parameter value is blank	Service profile
Parameter value is blank	Parameter value is set	Configuration file
Parameter value is blank	Parameter value is blank	Service profile blank (default) value

Group Configurations Using Cisco Support Field

Group configuration files apply to a subset of users. If you provision users with CSF devices, you can specify the group configuration file names in the **Cisco Support Field** field on the device configuration. If users do not have CSF devices, you can set a unique configuration file name for each group during installation with the TFTP_FILE_NAME argument.

Group configuration is supported on TCT and BOT with COP file later than 14122 version.



CHAPTER 6

Contact Source

- [Directory Servers, on page 79](#)
- [What is a Contact Source?, on page 80](#)
- [When to Configure Directory Integration, on page 80](#)
- [Why Do I Need a Contact Source?, on page 81](#)
- [Contact Source Options , on page 81](#)
- [LDAP Prerequisites, on page 85](#)
- [Jabber ID Attribute Mapping, on page 86](#)
- [Local Contact Sources, on page 87](#)
- [Custom Contact Sources, on page 87](#)
- [Contact Caching, on page 87](#)
- [Dial Plan Mapping, on page 87](#)
- [Cisco Unified Communication Manager UDS for Mobile and Remote Access, on page 88](#)
- [Cloud Contact Source, on page 88](#)
- [Contact Photo Formats and Dimensions, on page 88](#)

Directory Servers

You can use the following directory servers with Cisco Jabber:



Note

Cisco Jabber for Windows, Cisco Jabber for Mac, Cisco Jabber for iPhone and iPad, and Cisco Jabber for Android support the LDAPv3 standard for directory integration. Any directory server that supports this standard should be compatible with these clients.

- Active Directory Domain Services for Windows Server 2012 R2
- Active Directory Domain Services for Windows Server 2008 R2
- Cisco Unified Communications Manager User Data Server (UDS)

Cisco Jabber supports UDS using the following Cisco Unified Communications Manager versions:

Cisco Unified Communications Manager, version 9.1(2), with the following Cisco Options Package (COP) file: `cmterm-cucm-uds-912-5.cop.sgn`.

Cisco Unified Communications Manager, version 10.0(1). No COP file is required.

- OpenLDAP
- Active Directory Lightweight Directory Service (AD LDS) or Active Directory Application Mode (ADAM)

**Restriction**

Directory integration with OpenLDAP, AD LDS, or ADAM requires that you define specific parameters in a Cisco Jabber configuration file.

What is a Contact Source?

A contact source is a collection of data for users. When users search for contacts or add contacts in the Cisco Jabber client, the contact information is read from a contact source.

Cisco Jabber retrieves the information from the contact source to populate contact lists, update contact cards in the client and other areas that display contact information. When the client receives any incoming communications, for example an instant message or a voice/video call, the contact source is used to resolve the contact information.

When to Configure Directory Integration

**Note**

Install Cisco Jabber for Windows on a workstation that is registered to an Active Directory domain. In this environment, you do not need to configure Cisco Jabber for Windows to connect to the directory. The client automatically discovers the directory and connects to a Global Catalog server in that domain.

Configure Cisco Jabber to connect to a directory services if you plan to use one of the following services as the contact source:

- Domain Controller
- Cisco Unified Communications Manager User Data Service
- OpenLDAP
- Active Directory Lightweight Directory Service
- Active Directory Application Mode

You can optionally configure directory integration to:

- Change the default attribute mappings.
- Adjust directory query settings.
- Specify how the client retrieves contact photos.
- Perform intradomain federation.

Why Do I Need a Contact Source?

Cisco Jabber uses the contact source in the following ways:

- Users search for a contact—The client takes the information entered and searches in the contact source. Information is retrieved from the contact source and the client will display the available methods to interact with the contact.
- Client receives incoming notification—The client will take the information from the incoming notification and resolve the URI, number, JabberID with a contact from the contact source. The client will display the contact details in the alert.

Contact Source Options

In on-premises deployments, the client requires one of the following contact sources to resolve directory look ups for user information:

- Lightweight Directory Access Protocol (LDAP)—If you have a corporate directory, you can use the following LDAP-based contact source options to configure your directory as the contact source:
 - Enhanced Directory Integration (EDI)—Select this option to deploy Cisco Jabber for Windows.
 - Basic Directory Integration (BDI)—Select this option to deploy Cisco Jabber for Mac, iOS, and Android.
 - Cisco Directory Integration (CDI)—Use this contact source option to deploy all clients.
- Cisco Unified Communications Manager User Data Service (UDS)—If you do not have a corporate directory or if your deployment includes users connecting with Expressway Mobile and Remote Access, you can use this option.


LDAP Options: EDI and BDI

Enhanced Directory Integration

EDI uses native Microsoft Windows APIs to retrieve contact data from the directory service.

The following are the default settings for on-premises deployments with EDI:

- Cisco Jabber integrates with Active Directory as the contact source.
- Cisco Jabber automatically discovers and connects to a Global Catalog.



In the preceding diagram, the client does the following by default:

1. Gets the DNS domain from the workstation and looks up the SRV record for the Global Catalog.
2. Retrieves the address of the Global Catalog from the SRV record.
3. Connects to the Global Catalog with the logged in user's credentials.

Domain Name Retrieval

Cisco Jabber for Windows retrieves the fully qualified DNS domain from the `USERDNSDOMAIN` environment variable on the client workstation.

After the client gets the DNS domain, it can locate the Domain Name Server and retrieve SRV records.

If the `USERDNSDOMAIN` environment variable is not present, you can deploy the `LdapUserDomain` configuration parameter to specify which domain to execute the request for the LDAP service. If that parameter is not configured, then Jabber uses the domain from the email address screen.

In some instances, the value of the `USERDNSDOMAIN` environment variable does not resolve to the DNS domain that corresponds to the domain of the entire forest. For example, when an organization uses a sub-domain or resource domain. In this case, the `USERDNSDOMAIN` environment variable resolves to a child domain, not the parent domain. As a result, the client cannot access information for all users in the organization.

If the `USERDNSDOMAIN` environment variable resolves to a child domain, you can use one of the following options to enable Cisco Jabber for Windows to connect to a service in the parent domain:

- Ensure that the Global Catalog or LDAP directory server can access all users in the organization.
- Configure your DNS server to direct the client to a server that can access all users in the organization when Cisco Jabber for Windows requests a Global Catalog or LDAP directory server.
- Configure Cisco Jabber for Windows to use the FQDN of the domain controller.

Specify the FQDN of the domain controller as the value of the `PrimaryServerName` parameter in your client configuration as follows:

```
<PrimaryServerName>parent-domain-fqdn</PrimaryServerName>
```

Directory Server Discovery

Cisco Jabber can automatically discover and connect to the directory server if:

- The workstation on which you install Cisco Jabber automatically detects the workstation by determining the user domain.
- The workstation retrieves the server connection address from the DNS SRV record.

Directory Server	SRV Record
Global Catalog	<code>_gc._msdcs._tcp.domain.com</code>
Domain Controller LDAP-based directory servers	<code>_ldap._msdcs._tcp.domain.com</code>


Basic Directory Integration

The client retrieves contact data from the directory service as follows.

1. The client connects to the Cisco Unified Communication Manager IM and Presence Service node.
2. The client gets the LDAP profile configuration section in the service profile from the Cisco Unified Communication Manager IM and Presence Service node.

The service profile contains the location of Cisco Unified Communication Manager (TFTP) node. Depending on your configuration, the service profile can also contain the credentials to authenticate with the directory.
3. The client connects to the Cisco Unified Communication Manager node.
4. The client downloads the client configuration file from the Cisco Unified Communication Manager node.

The client configuration file contains the location of the directory. Depending on your configuration, the client configuration file can also contain the credentials to authenticate with the directory.
5. The client uses the directory location and the authentication credentials to connect to the directory.




Cisco Unified Communications Manager User Data Service

User Data Service (UDS) is a REST interface on Cisco Unified Communications Manager that provides contact resolution.

UDS is used for contact resolution in the following cases:

- If you set the `DirectoryServerType` parameter to use a value of UDS in the client configuration file.
With this configuration, the client uses UDS for contact resolution when it is inside or outside of the corporate firewall.
- If you deploy Expressway for Remote and Mobile Access.
With this configuration, the client automatically uses UDS for contact resolution when it is outside of the corporate firewall.

You synchronize contact data into Cisco Unified Communications Manager from a directory server. Cisco Jabber then automatically retrieves that contact data from UDS.



Contact Resolution with Multiple Clusters

For contact resolution with multiple Cisco Unified Communications Manager clusters, synchronize all users on the corporate directory to each cluster. Provision a subset of those users on the appropriate cluster.

For example, your organization has 40,000 users. 20,000 users reside in North America. 20,000 users reside in Europe. Your organization has the following Cisco Unified Communications Manager clusters for each location:

- `cucm-cluster-na` for North America
- `cucm-cluster-eu` for Europe

In this example, synchronize all 40,000 users to both clusters. Provision the 20,000 users in North America on `cucm-cluster-na` and the 20,000 users in Europe on `cucm-cluster-eu`.

When users in Europe call users in North America, Cisco Jabber retrieves the contact details for the user in Europe from `cucm-cluster-na`.

When users in North America call users in Europe, Cisco Jabber retrieves the contact details for the user in North America from `cucm-cluster-eu`.

LDAP Prerequisites

Cisco Jabber searches the contact source using various attributes, not all of these attributes are indexed by default. To ensure efficient searches the attributes used by Cisco Jabber must be indexed.

If you use the default attribute mappings, ensure the following attributes are indexed:

- `sAMAccountName`
- `displayName`

- sn
- name
- proxyAddresses
- mail
- department
- givenName
- telephoneNumber
- otherTelephone
- mobile
- homePhone
- msRTCSIP-PrimaryUserAddress

LDAP Service Account

Cisco Jabber uses an account to authenticate with the directory server. We recommend that this account has read-only access to the directory and is a commonly known public set of credentials.

Configure Cisco Jabber to connect to a directory server using a service profile or using parameters in the `jabber-config.xml` file. Cisco Jabber for all clients for Windows connects to a Global Catalog server by default and this is the recommended method for Cisco Jabber for all clients for Windows, you do not need to configure Cisco Jabber for all clients for Windows to connect to the directory.

Jabber ID Attribute Mapping

The LDAP attribute for user ID is `sAMAccountName`. This is the default attribute.

If the attribute for the user ID is other than `sAMAccountName`, and you're using the default IM address scheme in Cisco Unified Communications Manager IM and Presence Service, you must specify the attribute as the value for the parameter in your client configuration file as follows:

The EDI parameter is `UserAccountName`. `<UserAccountName>attribute-name</UserAccountName>`

The BDI parameter is `BDIUserAccountName`.

`<BDIUserAccountName>attribute-name</BDIUserAccountName>`

If you do not specify the attribute in your configuration, and the attribute is other than `sAMAccountName`, the client cannot resolve contacts in your directory. As a result, users do not get presence and cannot send or receive instant messages.

Search Jabber IDs

Cisco Jabber uses the Jabber ID to search for contact information in the directory. There are a few options to optimize searching in the directory:

- Search base—By default the client will start a search at the root of a directory tree. You can use search bases to specify a different search start or to restrict searches to specific groups. For example, a subset of your users have instant messaging capabilities only. Include those users in an OU and then specify that as a search base.
- Base Filter—Specify a directory subkey name only to retrieve objects other than user objects when you query the directory.
- Predictive Search Filter—You can define multiple, comma-separated values to filter search queries. The default value is ANR(Ambiguous name resolution.)

Local Contact Sources

Cisco Jabber has the ability to access and search local contact sources. These local contact sources include the following:

- Local contacts stored in Microsoft Outlook are accessed by Cisco Jabber for Windows.
- Local contacts stored in IBM Notes are accessed by Cisco Jabber for Windows (from release 11.1).
- Local address book contacts are accessed by Cisco Jabber for Mac, Cisco Jabber for Android and Cisco Jabber for iPhone and iPad.

Custom Contact Sources

Cisco Jabber for all clients for Windows provides users with the ability to import custom contacts into their client. For more information see the *Import contact lists* topic in the Cisco Jabber for all clients for Windows User Guide.

Contact Caching

Cisco Jabber creates a local cache of the users contact list. When a user searches for somebody in their contact list, Cisco Jabber searches the local cache for a match before starting a directory search.

If a user searches for somebody who is not in their contact list, Cisco Jabber will search the local cache for a match and then Cisco Jabber will search the company directory for a match. If the user starts a chat or a call with this contact, the contact information is added to the local cache. Subsequent searches for this contact will return the contact information in a *Contacts or recents* list.

The local cache information expires after 24 hours.

Dial Plan Mapping

You configure dial plan mapping to ensure that dialing rules on Cisco Unified Communications Manager match dialing rules on your directory.

Application Dial Rules

Application dial rules automatically add or remove digits in phone numbers that users dial. Application dialing rules manipulate numbers that users dial from the client.

For example, you can configure a dial rule that automatically adds the digit 9 to the start of a 7 digit phone number to provide access to outside lines.

Directory Lookup Dial Rules

Directory lookup dial rules transform caller ID numbers into numbers that the client can lookup in the directory. Each directory lookup rule you define specifies which numbers to transform based on the initial digits and the length of the number.

For example, you can create a directory lookup rule that automatically removes the area code and two-digit prefix digits from 10-digit phone numbers. An example of this type of rule is to transform 4089023139 into 23139.

Cisco Unified Communication Manager UDS for Mobile and Remote Access

Cisco Unified Communication Manager UDS is the contact source used when Cisco Jabber connects using Expressway for Mobile and Remote Access. If you deploy LDAP within the corporate firewall, we recommend that you synchronize your LDAP directory server with Cisco Unified Communications Manager to allow the client to connect with UDS when users are outside the corporate firewall.

Cloud Contact Source

Cisco Webex Contact Source

For Cloud deployments, contact data is configured in Cisco Webex Messenger Administration Tool or by user updates. The contact information can be imported using the Cisco Webex Messenger Administration Tool. For more information see the *User Management* section of the Cisco Webex Messenger Administration Guide.

Contact Photo Formats and Dimensions

To achieve the best result with Cisco Jabber, your contact photos should have specific formats and dimensions. Review supported formats and optimal dimensions. Learn about adjustments the client makes to contact photos.

Contact Photo Formats

Cisco Jabber supports the following formats for contact photos in your directory:

- JPG

- PNG
- BMP

**Important**

Cisco Jabber does not apply any modifications to enhance rendering for contact photos in GIF format. As a result, contact photos in GIF format might render incorrectly or with less than optimal quality. To obtain the best quality, use PNG format for your contact photos.

Contact Photo Dimensions

**Tip**

The optimum dimensions for contact photos are 128 pixels by 128 pixels with an aspect ratio of 1:1. 128 pixels by 128 pixels are the maximum dimensions for local contact photos in Microsoft Outlook.

The following table lists the different dimensions for contact photos in Cisco Jabber.

Location	Dimensions
Audio call window	128 pixels by 128 pixels
Invitations and reminders, for example: <ul style="list-style-type: none"> • Incoming call windows • Meeting reminder windows 	64 pixels by 64 pixels
Lists of contacts, for example: <ul style="list-style-type: none"> • Contact lists • Participant rosters • Call history • Voicemail messages 	32 pixels by 32 pixels

Contact Photo Adjustments

Cisco Jabber adjusts contact photos as follows:

- Resizing—If contact photos in your directory are smaller or larger than 128 pixels by 128 pixels, the client automatically resizes the photos. For example, contact photos in your directory are 64 pixels by 64 pixels. When Cisco Jabber retrieves the contact photos from your directory, it resizes the photos to 128 pixels by 128 pixels.



Tip Resizing contact photos can result in less than optimal resolution. For this reason, use contact photos that are 128 pixels by 128 pixels so that the client does not automatically resize them.

- **Cropping**—Cisco Jabber automatically crops nonsquare contact photos to a square aspect ratio, or an aspect ratio of 1:1 where the width is the same as the height.
- **Portrait orientation**—If contact photos in your directory have portrait orientation, the client crops 30 percent from the top and 70 percent from the bottom.

For example, if contact photos in your directory have a width of 100 pixels and a height of 200 pixels, Cisco Jabber needs to crop 100 pixels from the height to achieve an aspect ratio of 1:1. In this case, the client crops 30 pixels from the top of the photos and 70 pixels from the bottom of the photos.

- **Landscape orientation**—If contact photos in your directory have landscape orientation, the client crops 50 percent from each side.

For example, if contact photos in your directory have a width of 200 pixels and a height of 100 pixels, Cisco Jabber needs to crop 100 pixels from the width to achieve an aspect ratio of 1:1. In this case, the client crops 50 pixels from the right side of the photos and 50 pixels from the left side of the photos.



CHAPTER 7

Security and Certificates

- [Encryption, on page 91](#)
- [Voice and Video Encryption, on page 95](#)
- [Federal Information Processing Standards, on page 95](#)
- [Secure LDAP, on page 96](#)
- [Certificates, on page 97](#)

Encryption

Compliance and Policy Control for File Transfer and Screen Capture

If you send file transfers and screen captures using the Managed file transfer option on Cisco Unified Communications Manager IM and Presence 10.5(2) or later, you can send the files to a compliance server for audit and policy enforcement.

For more information about compliance, see the *Instant Messaging Compliance for IM and Presence Service on Cisco Unified Communications Manager* guide.

For more information about configuring file transfer and screen capture, see the *Cisco Unified Communications Manager IM and Presence Deployment and Installation Guide*.

Instant Message Encryption

Cisco Jabber uses Transport Layer Security (TLS) to secure Extensible Messaging and Presence Protocol (XMPP) traffic over the network between the client and server. Cisco Jabber encrypts point to point instant messages.

On-Premises Encryption

The following table summarizes the details for instant message encryption in on-premises deployments.

Connection	Protocol	Negotiation Certificate	Expected Encryption Algorithm
Client to server	XMPP over TLS v1.2	X.509 public key infrastructure certificate	AES 256 bit

Server and Client Negotiation

The following servers negotiate TLS encryption with Cisco Jabber using X.509 public key infrastructure (PKI) certificates with the following:

- Cisco Unified Communications Manager IM and Presence
- Cisco Unified Communications Manager

After the server and client negotiate TLS encryption, both the client and server generate and exchange session keys to encrypt instant messaging traffic.

The following table lists the PKI certificate key lengths for Cisco Unified Communications Manager IM and Presence Service.

Version	Key Length
Cisco Unified Communications Manager IM and Presence Service versions 9.0.1 and higher	2048 bit

XMPP Encryption

Cisco Unified Communications Manager IM and Presence Service uses 256-bit length session keys that are encrypted with the AES algorithm to secure instant message traffic between Cisco Jabber and the presence server.

If you require additional security for traffic between server nodes, you can configure XMPP security settings on Cisco Unified Communications Manager IM and Presence Service. See the following for more information about security settings:

- Cisco Unified Communications Manager IM and Presence Service—*Security configuration on IM and Presence*

Instant Message Logging

You can log and archive instant messages for compliance with regulatory guidelines. To log instant messages, you either configure an external database or integrate with a third-party compliance server. Cisco Unified Communications Manager IM and Presence Service does not encrypt instant messages that you log in external databases or in third party compliance servers. You must configure your external database or third party compliance server as appropriate to protect the instant messages that you log.

See the following for more information about compliance:

- Cisco Unified Communications Manager IM and Presence Service—*Instant Messaging Compliance for IM and Presence Service*

For more information about encryption levels and cryptographic algorithms, including symmetric key algorithms such as AES or public key algorithms such as RSA, see *Next Generation Encryption* at this link <https://www.cisco.com/c/en/us/about/security-center/next-generation-cryptography.html>.

For more information about X.509 public key infrastructure certificates, see the *Internet X.509 Public Key Infrastructure Certificate and CRL Profile* document at this link <https://www.ietf.org/rfc/rfc2459.txt>.

Cloud-Based Encryption

The following table summarizes the details for instant message encryption in cloud-based deployments:

Connection	Protocol	Negotiation Certificate	Expected Encryption Algorithm
Client to server	XMPP within TLS	X.509 public key infrastructure certificate	AES 128 bit
Client to client	XMPP within TLS	X.509 public key infrastructure certificate	AES 256 bit

Server and Client Negotiation

The following servers negotiate TLS encryption with Cisco Jabber using X.509 public key infrastructure (PKI) certificates with the Cisco Webex Messenger service.

After the server and client negotiate TLS encryption, both the client and server generate and exchange session keys to encrypt instant messaging traffic.

XMPP Encryption

The Cisco Webex Messenger service uses 128-bit session keys that are encrypted with the AES algorithm to secure instant message traffic between Cisco Jabber and the Cisco Webex Messenger service.

You can optionally enable 256-bit client-to-client AES encryption to secure the traffic between clients.

Instant Message Logging

The Cisco Webex Messenger service can log instant messages, but it does not archive those instant messages in an encrypted format. However, the Cisco Webex Messenger service uses stringent data center security, including SAE-16 and ISO-27001 audits, to protect the instant messages that it logs.

The Cisco Webex Messenger service cannot log instant messages if you enable AES 256 bit client-to-client encryption.

For more information about encryption levels and cryptographic algorithms, including symmetric key algorithms such as AES or public key algorithms such as RSA, see *Next Generation Encryption* at this link <https://www.cisco.com/c/en/us/about/security-center/next-generation-cryptography.html>.

For more information about X.509 public key infrastructure certificates, see the *Internet X.509 Public Key Infrastructure Certificate and CRL Profile* document at this link <https://www.ietf.org/rfc/rfc2459.txt>.

Client-to-Client Encryption

By default, instant messaging traffic between the client and the Cisco WebEx Messenger service is secure. You can optionally specify policies in the Cisco WebEx Administration Tool to secure instant messaging traffic between clients.

The following policies specify client-to-client encryption of instant messages:

- **Support AES Encoding For IM**—Sending clients encrypt instant messages with the AES 256-bit algorithm. Receiving clients decrypt instant messages.
- **Support No Encoding For IM**—Clients can send and receive instant messages to and from other clients that do not support encryption.

The following table describes the different combinations that you can set with these policies.

Policy Combination	Client-to-Client Encryption	When the Remote Client Supports AES Encryption	When the Remote Client Does not Support AES Encryption
Support AES Encoding For IM = false Support No Encoding For IM = true	No	Cisco Jabber sends unencrypted instant messages. Cisco Jabber does not negotiate a key exchange. As a result, other clients do not send Cisco Jabber encrypted instant messages.	Cisco Jabber sends and receives unencrypted instant messages.
Support AES Encoding For IM = true Support No Encoding For IM = true	Yes	Cisco Jabber sends and receives encrypted instant messages. Cisco Jabber displays an icon to indicate instant messages are encrypted.	Cisco Jabber sends encrypted instant messages. Cisco Jabber receives unencrypted instant messages.
Support AES Encoding For IM = true Support No Encoding For IM = false	Yes	Cisco Jabber sends and receives encrypted instant messages. Cisco Jabber displays an icon to indicate instant messages are encrypted.	Cisco Jabber does not send or receive instant messages to the remote client. Cisco Jabber displays an error message when users attempt to send instant messages to the remote client.



Note Cisco Jabber does not support client-to-client encryption with group chats. Cisco Jabber uses client-to-client encryption for point-to-point chats only.

For more information about encryption and Cisco WebEx policies, see *About Encryption Levels* in the Cisco WebEx documentation.

Encryption Icons

Review the icons that the client displays to indicate encryption levels.

Lock Icon for Client to Server Encryption

In both on-premises and cloud-based deployments, Cisco Jabber displays the following icon to indicate client to server encryption:



Padlock Icon for Client to Client Encryption

In cloud-based deployments, Cisco Jabber displays the following icon to indicate client to client encryption:



Local Chat History

Chat history is retained after participants close the chat window and until participants sign out. If you do not want to retain chat history after participants close the chat window, set the `Disable_IM_History` parameter to true. This parameter is available to all clients except IM-only users.

For on-premises deployment of Cisco Jabber for Mac, if you select the **Save chat archives to:** option in the **Chat Preferences** window of Cisco Jabber for Mac, chat history is stored locally in the Mac file system and can be searched using Spotlight.

Cisco Jabber does not encrypt archived instant messages when local chat history is enabled.

For mobile clients, you can disable local chat history if you do not want unencrypted instant messages to be stored locally.

For desktop clients, you can restrict access to chat history by saving archives to the following directories:

- Windows, `%USERPROFILE%\AppData\Local\Cisco\Unified Communications\Jabber\CSF\History\uri.db`
- Mac: `~/Library/Application Support/Cisco/Unified Communications/Jabber/CSF/History/uri.db`.

Voice and Video Encryption

You can optionally set up secure phone capabilities for all devices. Secure phone capabilities provide secure SIP signaling, secure media streams, and encrypted device configuration files.

If you enable secure phone capabilities for users, device connections to Cisco Unified Communications Manager are secure. However, calls with other devices are secure only if both devices have a secure connection.

Federal Information Processing Standards



Note This section applies to Cisco Jabber for Windows only.

The Federal Information Processing Standard (FIPS) 140 is a U.S. and Canadian government standard that specifies security requirements for cryptographic modules. These cryptographic modules include the set of hardware, software, and firmware that implements approved security functions and is contained within the cryptographic boundary.

FIPS requires that all encryption, key exchange, digital signatures, and hash and random number generation functions used within the client are compliant with the FIPS 140.2 requirements for the security of cryptographic modules.

FIPS mode results in the client managing certificates more strictly. Users in FIPS mode may see certificate errors in the client if a certificate for a service expires and they haven't reentered their credentials. Users also see a FIPS icon in their hub window to indicate that the client is running in FIPS mode.

Enable FIPS for Cisco Jabber for Windows



Note The Screen Share feature is not supported if FIPS mode is enabled.

Cisco Jabber for Windows supports two methods of enabling FIPS:

- Operating system enabled—The Windows operating system is in FIPS mode.
- Cisco Jabber bootstrap setting—Configure the FIPS_MODE installer switch. Cisco Jabber can be in FIPS mode on an operating system that is not FIPS enabled. In this scenario, only connections with non-Windows APIs are in FIPS mode.

Table 9: Cisco Jabber for Windows Setting for FIPS

Platform Mode	Bootstrap Setting	Cisco Jabber Client Setting
FIPS Enabled	FIPS Enabled	FIPS Enabled—Bootstrap setting.
FIPS Enabled	FIPS Disabled	FIPS Disabled—Bootstrap setting.
FIPS Enabled	No setting	FIPS Enabled—Platform setting.
FIPS Disabled	FIPS Enabled	FIPS Enabled—Bootstrap setting.
FIPS Disabled	FIPS Disabled	FIPS Disabled—Bootstrap setting.
FIPS Disabled	No setting	FIPS Disabled—Platform setting.



Note Jabber Voicemail service only accepts TLS Version TLS 1.2 for HTTPs request **https://164.62.224.15/vmrest/version with FIPS enabled** during an SSL connection.

Secure LDAP

Secure LDAP communication is LDAP over SSL/TLS

LDAPS initiates an LDAP connection over a SSL/TLS connection. It opens the SSL session then begins using the LDAP protocol. This requires a separate port, 636 or Global Catalog port 3269.

Certificates

Certificate Validation

The Certificate Validation Process

Cisco Jabber validates server certificates when authenticating to services. When attempting to establish secure connections, the services present Cisco Jabber with certificates. Cisco Jabber validates the presented certificate against what is in the client device's local certificate store. If the certificate is not in the certificate store, the certificate is deemed untrusted and Cisco Jabber prompts the user to accept or decline the certificate.

If the user accepts the certificate, Cisco Jabber connects to the service and saves the certificate in the certificate store or keychain of the device. If the user declines the certificate, Cisco Jabber does not connect to the service and the certificate is not saved to the certificate store or keychain of the device.

If the certificate is in the local certificate store of the device, Cisco Jabber trusts the certificate. Cisco Jabber connects to the service without prompting the user to accept or decline the certificate.

Cisco Jabber authenticates to two services on the Cisco Unified Communications Manager server. The service names are Cisco Tomcat and Extensible Messaging and Presence Protocol (XMPP). A certificate signing request (CSR) must be generated for each service. Some public certificate authorities do not accept more than one CSR per fully qualified domain name (FQDN). Which means that the CSR for each service may need to be sent to separate public certificate authorities.

Ensure that you specify FQDN in the service profile for each service, instead of the IP address or hostname.

Signed Certificates

Certificates can be signed by the certificate authority (CA) or self-signed.

- CA-signed certificates—Users are not prompted because you are installing the certificate on the devices yourself. CA-signed certificates can be signed by a Private CA or a Public CA. Many certificates that are signed by a Public CA are stored in the certificate store or keychain of the device.
- Self-signed certificates—Certificates are signed by the services that are presenting the certificates, and users are always prompted to accept or decline the certificate.



Note We recommend that you don't use self-signed certificates.

Certificate Validation Options

Before setting up certificate validation, you must decide how you want the certificates to be validated:

- Whether you are deploying certificates for on-premises or cloud-based deployments.
- What method you are using to sign the certificates.
- If are you deploying CA-signed certificates, whether you are going to use public CA or private CA.
- Which services you need to get certificates for.

Required Certificates for On-Premises Servers

On-premises servers present the following certificates to establish a secure connection with Cisco Jabber:

Server	Certificate
Cisco Unified Communications Manager IM and Presence Service	HTTP (Tomcat) XMPP
Cisco Unified Communications Manager	HTTP (Tomcat) and CallManager certificate (secure SIP call signaling for secure phone)
Cisco Unity Connection	HTTP (Tomcat)
Cisco Webex Meetings Server	HTTP (Tomcat)
Cisco VCS Expressway Cisco Expressway-E	Server certificate (used for HTTP, XMPP, and SIP call signaling)

Important Notes

- Security Assertion Markup Language (SAML) single sign-on (SSO) and the Identity Provider (IdP) require an X.509 certificate.
- You should apply the most recent Service Update (SU) for Cisco Unified Communications Manager IM and Presence Service before you begin the certificate signing process.
- The required certificates apply to all server versions.
- Each cluster node, subscriber, and publisher, runs a Tomcat service and can present the client with an HTTP certificate.

You should plan to sign the certificates for each node in the cluster.

- To secure SIP signaling between the client and Cisco Unified Communications Manager, you should use Certification Authority Proxy Function (CAPF) enrollment.

Certificate Signing Request Formats and Requirements

A public certificate authority (CA) typically requires a certificate signing request (CSR) to conform to specific formats. For example, a public CA might only accept CSRs that have the following requirements:

- Are Base64-encoded.
- Do not contain certain characters, such as @ & !, in the **Organization**, **OU**, or other fields.
- Use specific bit lengths in the server's public key.

If you submit CSRs from multiple nodes, public CAs might require that the information is consistent in all CSRs.

To prevent issues with your CSRs, you should review the format requirements from the public CA to which you plan to submit the CSRs. You should then ensure that the information you enter when configuring your server conforms to the format that the public CA requires.

One Certificate Per FQDN—Some public CAs sign only one certificate per fully qualified domain name (FQDN).

For example, to sign the HTTP and XMPP certificates for a single Cisco Unified Communications Manager IM and Presence Service node, you might need to submit each CSR to different public CAs.

Revocation Servers

Cisco Jabber cannot connect to the Cisco Unified Communications Manager servers if the revocation server is not reachable. Also, if a certificate authority (CA) revokes a certificate, Cisco Jabber does not allow users to connect to that server.

Users are not notified of the following outcomes:

- The certificates do not contain revocation information.
- The revocation server cannot be reached.

To validate certificates, the certificate must contain an HTTP URL in the **CDP** or **AIA** fields for a reachable server that can provide revocation information.

To ensure that your certificates are validated when you get a certificate issued by a CA, you must meet one of the following requirements:

- Ensure that the **CRL Distribution Point (CDP)** field contains an HTTP URL to a certificate revocation list (CRL) on a revocation server.
- Ensure that the **Authority Information Access (AIA)** field contains an HTTP URL for an Online Certificate Status Protocol (OCSP) server.

Server Identity in Certificates

As part of the signing process, the CA specifies the server identity in the certificate. When the client validates that certificate, it checks that:

- A trusted authority has issued the certificate.
- The identity of the server that presents the certificate matches the identity of the server specified in the certificate.



Note Public CAs generally require a fully qualified domain name (FQDN) as the server identity, not an IP address.

Identifier Fields

The client checks the following identifier fields in server certificates for an identity match:

- XMPP certificates
 - SubjectAltName\OtherName\xmppAddr
 - SubjectAltName\OtherName\srvName
 - SubjectAltName\dnsNames
 - Subject CN

- HTTP certificates
 - SubjectAltName\dnNames
 - Subject CN

**Tip**

The Subject CN field can contain a wildcard (*) as the leftmost character, for example, *.cisco.com.

Prevent Identity Mismatch

If users attempt to connect to a server with an IP address or hostname, and the server certificate identifies the server with an FQDN, the client cannot identify the server as trusted and prompts the user.

If your server certificates identify the servers with FQDNs, you should plan to specify each server name as FQDN in many places on your servers. For more information, see *Prevent Identity Mismatch* section in [Troubleshooting TechNotes](#).

Certificates for Multiserver SANs

If you use a multiserver SAN, you only need to upload a certificate to the service once per cluster per tomcat certificate and once per cluster per XMPP certificate. If you do not use a multiserver SAN, then you must upload the certificate to the service for every Cisco Unified Communications Manager node.

Certificate Validation for Cloud Deployments

Cisco Webex Messenger and Cisco Webex Meetings Center present the following certificates to the client by default:

- CAS
- WAPI

**Note**

Cisco Webex certificates are signed by a public Certificate Authority (CA). Cisco Jabber validates these certificates to establish secure connections with cloud-based services.

Cisco Jabber validates the following XMPP certificates received from Cisco Webex Messenger. If these certificates are not included in your operating system, you must provide them.

- VeriSign Class 3 Public Primary Certification Authority - G5 — This certificate is stored in the Trusted Root Certificate Authority
- VeriSign Class 3 Secure Server CA - G3 — This certificate validates the Webex Messenger server identity and is stored in the Intermediate Certificate Authority.
- AddTrust External CA Root
- GoDaddy Class 2 Certification Authority Root Certificate

For more information about root certificates for Cisco Jabber for Windows, see <https://www.identrust.co.uk/certificates/trustid/install-nes36.html>.

For more information about root certificates for Cisco Jabber for Mac, see <https://support.apple.com>.



CHAPTER 8

Screen Share

- [Screen Share, on page 103](#)

Screen Share

There are four types of screen share:

- Cisco WebEx share
- BFCP share
- IM Only share
- Escalate to a meeting and share

Cisco Webex Screen Share

Applies to Cisco Jabber for desktop clients in cloud deployments.

For cloud deployments, Cisco Webex Screen Share is selected automatically after choosing a contact, if BFCP and IM Only screen share options are not available.

You can start Cisco Webex Screen Share using one of the following methods:

- Right-click on a contact in the hub window and choose **Share screen..** from the menu options.
- Select a contact in the hub window and click on the **Settings** menu. Choose **Communicate** and select **Share screen...** from the menu options.
- When BFCP and IM Only screen share options are not available, then in a conversation window select **... > Share screen** from the menu options.

BFCP Screen Share

Applies to Cisco Jabber desktop clients, Cisco Jabber for mobile clients can only receive BFCP screen shares.

Binary Floor Control Protocol (BFCP) screen share is controlled by Cisco Unified Communications Manager. Cisco Unified Communications Manager handles the BFCP packets that users transmit when using video desktop sharing capabilities. When on a call select **... > Share screen** to start a BFCP screen share.

Remote screen control is not supported with this feature.

IM Only Screen Share

Applies to Cisco Jabber for Windows.

IM Only screen share is a one to one screen share and is enabled using the EnableP2PDesktopShare parameter in the jabber-config.xml file. In a chat window users select ... > **Share screen**.

The port range for this option is 49152 to 65535 and this can be reduced by using the SharePortRangeStart and SharePortRangeSize parameters in the jabber-config.xml file.

Escalate to a Meeting and Share

Applies to all Cisco Jabber clients.

You can escalate to an instant Cisco Webex Meetings and share your screen using the Cisco Webex Meetings controls.



CHAPTER 9

Federation

- [Interdomain Federation, on page 105](#)
- [Intradomain Federation, on page 106](#)
- [User ID Planning for Federation, on page 106](#)

Interdomain Federation

Interdomain federation enables Cisco Jabber users in an enterprise domain to share availability and send instant messages with users in another domain.

- Cisco Jabber users must manually enter contacts from another domain.
- Cisco Jabber supports federation with the following:
 - Microsoft Office Communications Server
 - Microsoft Lync
 - IBM Sametime
 - XMPP standard-based environments such as Google Talk



Note Expressway for Mobile and Remote Access doesn't enable XMPP Interdomain federation itself. Cisco Jabber clients connecting over Expressway for Mobile and Remote Access can use XMPP Interdomain federation if it has been enabled on Cisco Unified Communications Manager IM and Presence.

- AOL Instant Messenger

You configure interdomain federation for Cisco Jabber on Cisco Unified Communications Manager IM and Presence Service. See the appropriate server documentation for more information.

Intradomain Federation

Intradomain federation enables users within the same domain to share availability and send instant messages between Cisco Unified Communications Manager IM and Presence Service and Microsoft Office Communications Server, Microsoft Live Communications Server, or another presence server.

Intradomain federation allows you to migrate users to Cisco Unified Communications Manager IM and Presence Service from a different presence server. For this reason, you configure intradomain federation for Cisco Jabber on the presence server. See the following for more information:

- Cisco Unified Communications Manager IM and Presence Service: *Partitioned Intradomain Federation for IM and Presence Service on Cisco Unified Communications Manager*

User ID Planning for Federation

For federation, Cisco Jabber requires the contact ID or user ID for each user to resolve contacts during contact searches.

In the `jabber-config.xml` file you set the attribute for the user ID in the `SipUri BDISipUri` parameter. The default value is `msRTCSIP-PrimaryUserAddress`. If there is a prefix to remove from your user ID you can set a value in the `UriPrefix BDIUriPrefix` parameter.