



# **DYNAMIC MULTIPOINT VPN HUB AND SPOKE INTRODUCTION**

**NOVEMBER 2004**


# INTRODUCTION



# What is Dynamic Multipoint VPN ?

- **Dynamic Multipoint VPN (DMVPN) is a combination of GRE, NHRP, and IPsec**
- **NHRP allows the peers to have dynamic addresses (ie: Dial and DSL) with GRE / IPsec tunnels**
- **Backbone is a hub and spoke topology**
- **Allows direct spoke to spoke tunneling by auto leveling to a partial mesh**

# Site-to-Site, DMVPN: mGRE/IPsec/NHRP Integration, Only HUB address Is Known



# Terminology Pause

- **DMVPN is a partial dynamic mesh**

**Spoke:** all the devices that contact a central router called “**hub**”

**Node:** any hub or a spoke

# This Presentation

- This presentation concentrate on hub and spoke to explain **how DMVPN works**

# DMVPN



# GRE Tunnels

- **A GRE tunnel is a simple non-negotiated tunnel; GRE only needs tunnel endpoints**
- **GRE encapsulate frames or packets into an other IP packet + IP header**
- **GRE has only 4 to 8 bytes of overhead**
- **GRE tunnels exist in two main flavors:**
  - Point-to-point (GRE)**
  - Point-to-multipoint (mGRE)**



# GRE multipoint and DMVPN

- **A GRE interface definition includes**

- An IP address

- A tunnel source

- A tunnel destination

- An optional tunnel key

```
interface Tunnel 0
  ip address 10.0.0.1 255.0.0.0
  tunnel source Dialer1
  tunnel destination 172.16.0.2
  tunnel key 1
```

- **An mGRE interface definition includes**

- An IP address

- A tunnel source

- A tunnel key

```
interface Tunnel 0
  ip address 10.0.0.1 255.0.0.0
  tunnel source Dialer1
  tunnel mode gre multipoint
  tunnel key 1
```

- **mGRE interfaces do **not** have a tunnel destination**

# Terminology Pause

- The **tunnel address** is the ip address defined on the tunnel interface
- The **Non-Broadcast Multiple Access (NBMA) address** is the ip address used as tunnel source (or destination)
- **Example... on router A, one configures**

```
interface Ethernet0/0
  ip address 172.16.0.1 255.255.255.0
interface Tunnel0
  ip address 10.0.0.1 255.0.0.0
  tunnel source Ethernet0/0
  [...]
```


**10.0.0.1** is router A's **tunnel address**

**172.16.0.1** is router A's **NBMA address**

# mGRE Tunnels

- **Single tunnel interface (mp)**
  - Non-Broadcast Multi-Access (NBMA) Network**
  - Multiple (dynamic) tunnel destinations**
  - Multicast/broadcast support**
- **Next Hop Resolution Protocol (NHRP)**
  - VPN IP to NBMA IP address mapping**

# GRE Encapsulation



# DMVPN GRE Interfaces

- In DMVPN, the hub **must** have a point to mGRE
- Spokes **can** have a point to point GRE interface or an mGRE interface
- This presentation will use mGRE everywhere for consistency
- Note that point-to-point GRE interfaces prevent spoke to spoke direct tunneling

# mGRE Talking to a Peer

- Because mGRE tunnels do **not** have a tunnel destination defined, they can not be used alone
- **NHRP** tells mGRE where to send the packets to
- **NHRP** is defined in RFC 2332

# What is NHRP?


- NHRP is a layer two resolution protocol and cache like ARP or Reverse ARP (Frame Relay)
- It is used in DMVPN to map a **tunnel IP address to an NBMA address**
- Like ARP, NHRP can have static and dynamic entries
- NHRP has worked fully dynamically since Release 12.2(13)T

# How mGRE Uses NHRP

- When a packet is routed, it is passed to the mGRE interface along with a next-hop
- The next-hop is the tunnel address of a remote peer
- mGRE looks up the **NHRP cache** for the next-hop address and retrieves the NBMA address of the remote peer
- mGRE encapsulates the packet into a GRE/IP payload
- The new packet destination is the NBMA address
- Multicast packets are only sent to **specific remote peers** identified in the NHRP configuration




# mGRE/NHRP Path



# How NHRP Works

- **mGRE uses NHRP**, but how does NHRP work?
- This presentation will introduce a network topology and illustrate the associated **NHRP commands**

# NHRP Registration Dynamically Addressed Spokes



# Basic NHRP Configuration

- In order to configure an mGRE interface to use NHRP, the following command is necessary:

```
ip nhrp network-id <id>
```

- Where <id> is a unique number (same on hub and all spokes)
- <id> has nothing to do with tunnel key
- The network ID defines an NHRP domain  
Several domains can co-exist on the same router

# Populating the NHRP Cache

- **Three ways to populate the NHRP cache:**
  - Manually add **static** entries
  - Hub learns via **registration** requests
  - Spokes learn via **resolution** requests
- **We will now study “static” and “registration”**
- **“Resolution” is for spoke to spoke**

# Initial NHRP Caches

- Initially, the hub has an empty cache
- The spoke has one static entry mapping the hub's tunnel address to the hub's NBMA address:

```
ip nhrp map 10.0.0.1 172.17.0.1
```

- Multicast traffic must be sent to the hub

```
ip nhrp map multicast 172.17.0.1
```

# The Spokes Must Register To The Hub

- In order for the spokes to register themselves to the hub, the hub must be declared as a Next Hop Server (NHS):

```
ip nhrp nhs 10.0.0.1
```

```
ip nhrp holdtime 3600 (optional)
```

```
ip nhrp registration no-unique (optional)
```

- Spokes control the cache on the hub

# Registration Process

- The spokes send **Registration-requests** to the hub
- The request contains the spoke's **Tunnel and NBMA** addresses as well as the hold time and some flags
- The hub creates an entry in its NHRP cache
- The entry will be valid for the duration of the **hold time defined in the registration**
- The NHS returns a **registration reply** (acknowledgement)




# Multicast Packets from the Hub

- The hub must also send multicast traffic to all the spokes that registered to it
- This **must** be done dynamically (possible since Release 12.2(13)T)
- This is **not** the default

```
ip nhrp map multicast dynamic
```


# NHRP Registration Request



# NHRP Registration Reply


192.168.0.1/24

Physical: 172.17.0.1  
Tunnel0: 10.0.0.1




## NHRP Table

10.0.0.11 -> 172.16.1.1  
(dynamic, mcast, hold=3600, no-unique)



Physical: (dynamic)172.16.1.1  
Tunnel0: 10.0.0.11



## NHRP Table

10.0.0.1 -> 172.17.0.1  
(static, mcast)

# NHRP Functionality

- **Address mapping/resolution**

  - Static NHRP mapping**

  - Next Hop Client (NHC) registration with Next Hop Server (NHS)**

- **Packet Forwarding**

  - Resolution of VPN to NBMA mapping**

    - Routing: IP destination → Tunnel IP next-hop**

    - NHRP: Tunnel IP next-hop → NBMA address**

# Routing Protocol

- **The spoke needs to advertise its private network to the hub**
- **Can use BGP, EIGRP, OSPF, RIP or ODR; however, this presentation will focus on EIGRP**
- **Must consider several caveats**

# Spoke Hellos

- **Spoke has all it needs to send hellos immediately:**
  - Tunnel is defined**
  - Static NHRP entry to hub is present**
  - NHRP entry is marked for multicast**
- **So the spoke never waits...**

# Hub hello's

- With its basic tunnel definition, the hub **cannot send anything** (including hellos) to anyone
- It must wait NHRP for registrations to arrive
- As soon as the spokes have registered, the NHRP is marked “Multicast” due to


```
ip nhrp map multicast dynamic
```

- The hub sends hellos to **all the registered spokes simultaneously**

# Hub sending EIGRP hello



192.168.0.1/24

Physical: 172.17.0.1  
Tunnel0: 10.0.0.1



## NHRP Table

10.0.0.11 -> 172.16.1.1  
(dynamic, mcast, hold=3600, no-unique)



Physical: (dynamic)172.16.1.1  
Tunnel0: 10.0.0.11



**EIGRP neighbor  
10.0.0.1**

## NHRP Table

10.0.0.1 -> 172.17.0.1  
(static, mcast)



# GRE and EIGRP

- The **default** bandwidth of a GRE tunnel is 9Kbps
- This has no influence on the traffic but...
- **EIGRP will take 1/2 the interface bandwidth maximum (4.5 Kbps) – this is too low**

```
bandwidth 1000
```

# Spoke EIGRP configuration

- **Nothing special on the spoke**
- **EIGRP stub should be considered**

# Hub EIGRP Configuration

- There are many options...
- If you want a spoke to see other spokes:  

```
no ip split-horizon eigrp 1
```
- Summarization is to be considered
- Setting the **bandwidth** is crucial in the hub to spoke direction
- Best-practice: Set the bandwidth the same on all nodes

# IPsec Protection

- **GRE/NHRP can build a fully functional overlay network**
- **GRE is insecure; ideally, it must be protected**
- **The good old crypto map configuration is rather cumbersome; DMVPN introduced **tunnel protection****
- **Still need to define an IPsec security level**

# The IPsec Security Policy

- **A transform set must be defined:**

```
crypto ipsec transform-set ts esp-sha-hmac esp-3des
mode transport
```

- **An IPsec profile replaces the crypto map**

```
crypto ipsec profile prof
set transform-set ts
```

- **The IPsec profile is like a crypto map without “set peer” and “match address”**

# Protecting the tunnel

- The profile must be applied on the tunnel

```
tunnel protection ipsec profile prof
```

- Internally Cisco IOS® Software will treat this as a dynamic crypto map and it derives the local-address, set peer and match address parameters from the **tunnel parameters** and the **NHRP cache**
- This must be configured on the hub **and** spoke tunnels

# Relation Between GRE, NHRP and IPsec

- **For each NHRP cache unique NBMA address, Cisco IOS Software will create an internal crypto map that protects**
  - GRE traffic**
  - From tunnel source (NBMA) address**
  - To NHRP entry NBMA address**
- **The SAs will be negotiated as soon as the cache entry is created (static and resolved)**

# Relationship (cont'd.)

- **NHRP registration will be triggered**

**When the Tunnel interface comes up/up**


**When the tunnel source address changes**

**When IPsec finishes negotiating the phase 2 related to the tunnel protection**

**When the registration timer expires**




# NHRP Registration Dynamically Addressed Spokes



# Building Hub-and-Spoke tunnels

## NHRP Registration



# CISCO SYSTEMS

