



# Date\_with\_Confirm

The `Date_With_Confirm` voice element captures a date input from the caller, and presents a confirmation menu allowing the caller to either accept their entry or re-enter the date. The date can be entered using DTMF input (in the YYYYMMDD format). It can also be spoken in natural language including a month, day and year. The captured value will be stored in element data as a fixed-length date string in the YYYYMMDD format. If the year is not specified in the input, YYYY is stored as “????”. If the month or the day is not specified, MM and DD will be stored as “??”.

- [Settings, on page 1](#)
- [Element Data, on page 2](#)
- [Exit States, on page 3](#)
- [Audio Groups, on page 4](#)
- [Folder and Class Information, on page 5](#)
- [Events, on page 5](#)

## Settings

Name (Label)	Type	Req'd	Single Setting Value	Substitution Allowed	Default	Notes
inputmode (Input Mode)	string enum	Yes	true	false	both	The type of entry allowed for input. Possible values are: voice   dtmf   both.
noinput_timeout (Noinput Timeout)	string	Yes	true	true	5s	The maximum time length allowed for silence or no keypress before a noinput event is thrown. Possible values are standard time designations including both a non-negative number and a time unit, for example, 3s (for seconds) or 3000ms (for milliseconds). Default = 5s.
collect_max_noinput_count (Date Max NoInput Count)	int ≥ 0	Yes	true	true	3	The maximum number of noinput events allowed during date input capture. 0 = infinite noinputs allowed.

collect_max_nomatch_count (Date Max NoMatch Count)	int $\geq 0$	Yes	true	false	3	The maximum number of nomatch events allowed during date input capture. 0 = infinite nomatches allowed.
confirm_max_noinput_count (Confirm Max NoInput Count)	int $\geq 0$	Yes	true	true	3	The maximum number of noinput events allowed during date input confirmation. 0 = infinite noinputs allowed.
confirm_max_nomatch_count (Confirm Max NoMatch Count)	int $\geq 0$	Yes	true	false	3	The maximum number of nomatch events allowed during date input confirmation. 0 = infinite nomatches allowed.
max_disconfirmed_count (Max Disconfirmed Count)	int $\geq 0$	Yes	true	false	3	The maximum number of times a caller is allowed to disconfirm a captured input. 0 = infinite disconfirmations allowed.
collect_confidence_level (Date Confidence Level)	decimal (0.0 – 1.0)	Yes	true	false	0.40	The confidence level threshold to use during date capture.
confirm_confidence_level (Confirm Confidence Level)	decimal (0.0 – 1.0)	Yes	true	false	0.50	The confidence level threshold to use during confirmation.
modal (Disable Hotlinks)	boolean	Yes	true	false	false	If set to true, only the grammars of the current Date_With_Confirm element (the built-in date and boolean grammars) will be enabled for the duration of the element. Otherwise all active grammars will be enabled.
secure_logging (Secure Logging)	boolean	Yes	true	false	false	If set to true, user DTMF input for the element is considered secure and the attributes utterance, interpretation, value, nbestUtteranceX and nbestInterpretationX are masked in VXML server logs. The format used to render secure element attributes is to add a <i>_secureLogging</i> suffix. For example <code>nbestUtterance1_secureLogging,*****.</code>
maxnbest (Maxnbest)	int $\geq 1$	Yes	true	false	1	The maximum number of speech recognition results that can be generated per voice input.

Refer to the following Element Data table for information about nbestUtteranceX and nbestInterpretationX.

## Element Data

Name	Type	Notes
------	------	-------

value	string	The date stored in the YYYYMMDD format.
value_confidence	float	This is the confidence value of the captured date utterance. When n-best recognition is enabled, this stores the confidence score of the top hypothesis in the n-best list.
confirm_confidence	float	This is the confidence value of the captured confirm utterance.
nbestLength	int $\geq 1$	This stores the number of n-best hypotheses generated by the speech engine.
nbestUtterance1 nbestUtterance2 ... nbestUtteranceX	string	This set of element data stores the captured n-best utterances. While the maximum number of nbestUtteranceX values is equal to the maxnbest setting value, the actual number of these values available is determined by speech recognition at runtime, where nbestUtterance1 holds the utterance of the top hypothesis in the n-best list and nbestUtteranceX holds the utterance of the last hypothesis.
nbestInterpretation1 nbestInterpretation2 ... nbestInterpretationX	string	This set of element data stores the interpretations of captured n-best utterances. While the maximum number of nbestInterpretationX values is equal to the maxnbest setting value, the actual number of these values available is determined by speech recognition at runtime, where nbestInterpretation1 holds the interpretation of the top hypothesis in the n-best list and nbestInterpretationX holds the interpretation of the last hypothesis.
nbestConfidence1 nbestConfidence2 ... nbestConfidenceX	float	This set of element data stores the confidence scores of captured n-best utterances. While the maximum number of nbestConfidenceX values is equal to the maxnbest setting value, the actual number of these values available is determined by speech recognition at runtime, where nbestConfidence1 holds the confidence score of the top hypothesis in the n-best list and nbestConfidenceX holds the confidence score of the last hypothesis.
nbestInputmode1 nbestInputmode2 ... nbestInputmodeX	string	This set of element data stores the input modes of captured n-best utterances.

## Exit States

Name	Notes
max_nomatch	The maximum number of nomatch events has occurred. If the max nomatch count is 0, this exit state will never occur.
max_noinput	The maximum number of noinput events has occurred. If the max noinput count is 0, this exit state will never occur.

max_disconfirmed	The maximum number of disconfirmations occurred. If the <code>max_disconfirmed_count</code> is set to 0, this exit state will never occur.
done	The date captured was confirmed.

## Audio Groups

### Date Capture

Name (Label)	Req'd	Max 1	Notes
collect_initial_audio_group (Date Initial)	Yes	Yes	Played when the voice element first begins.
collect_noinput_audio_group (Date NoInput)	No	No	Played when a noinput event occurs during date input. The noinput event count corresponds to the audio group count.
collect_nomatch_audio_group (Date NoMatch)	No	No	Played when a nomatch event occurs during date input. The nomatch event count corresponds to the audio group count.
collect_help_audio_group (Date Help)	No	No	Played when a help event occurs during date input. The help event count corresponds to the audio group count. If not specified, a help event is treated as nomatch.

### Date Confirm

Name (Label)	Req'd	Max 1	Notes
confirm_initial_audio_group (Confirm Initial)	Yes	Yes	Played when the captured date is confirmed.
confirm_noinput_audio_group (Confirm NoInput)	No	No	Played when a noinput event occurs during date confirmation. The noinput event count corresponds to the audio group count.
confirm_nomatch_audio_group (Confirm NoMatch)	No	No	Played when a nomatch event occurs during date confirmation. The nomatch event count corresponds to the audio group count.
confirm_help_audio_group (Confirm Help)	No	No	Played when a help event occurs during date confirmation. The help event count corresponds to the audio group count. If not specified, by default help is treated as nomatch.

disconfirmed_audio_group (Disconfirmed)	No	No	Played after the caller disconfirms a date entry.
--	----	----	---

## End

Name (Label)	Req'd	Max 1	Notes
yes_audio_group (Yes)	No	Yes	Played after the caller chooses the <i>yes</i> option. If not specified, no audio will be played when this option is chosen.

## Folder and Class Information

Studio Element Folder Name	Class Name
Date & Time	com.audium.server.voiceElement.date.MBasicDateWithConfirm

## Events

Name (Label)	Notes
Event Type	You can select <b>Java Exception</b> , <b>VXML Event</b> , or <b>Hotlink</b> as event handler for this element.

