

# IEA版本6.3许可证密钥

## 目录

### [简介](#)

### [使用静态IP地址Licensekey更新](#)

### [手工安装密钥](#)

## 简介

IronPort加密设备(IEA)版本6.3或以后检查一次每天新的密钥。如果它查找新的密钥，将相应地更新许可证文件。此进程是在端口80的一呼出从IEA到http://downloads-static.ironport.com (默认情况下)。

要验证密钥的状况在IEA GUI的，请去**霍姆>监控服务器**。您将看到被提交的许可证信息。

只要安排，许可证密钥下载将发生日报他们。它设置一天一次运行。看到日程去**Administration > Scheduled Tasks**。使用**运行按钮**，您能**当前运行任务**。

## 使用静态IP地址Licensekey更新

如果需要使用从IEA的一静态IP更新，需要修改两个文件使用http://downloads-static.ironport.com (204.15.82.8)。

1. 更改在pxeconfg.xml的链路。编辑线路：`<entry desc=" $msg.svc.scheduler.licenseremind.url.desc" label=" $msg.svc.scheduler.licenseremind.url.label" name=" URL" required="1" value=" http://downloads.ironport.com/asyncos/fkey"/>`更改“http://downloads.ironport.com/asyncos/fkey”对“http://downloads-static.ironport.com/asyncos/fkey”。
2. 编辑在/usr/local/postx/server\_6.3/conf/lm目录查找的postx.license文件。更改“http://downloads.ironport.com/asyncos/fkey”对“http://downloads-static.ironport.com/asyncos/fkey”。

## 手工安装密钥

- 对设备和'su的SSH -'根源(命中数'x'从下降到的admin菜单shell;注释此是在6.3的一个隐藏的选项)。
- 运行'managelicense.sh' shell script程序以-importKey选项是什么您将需要使用安装新的密钥。您将必须运行其中每一的命令您需要安装的新的许可证。

示例：

```
$ ssh admin@myiea.local
```

```
admin@myiea.local's password:
Last login: Wed Sep 17 15:47:38 2014 from myhost.local
=====
Please select from the following menu options.
```

**S) System Setup - First time system setup**

- 1) Configure Network
- 2) Configure TimeServer
- 3) Change Password
- 4) Encryption Server Re-Initialize
- 5) Restart Operating System
- 6) Shutdown (halt) Operating System
  
- g) Search Mail Logs (grep) - q to exit
- t) View Encryption Server Logs (tail) - <ctrl-c> to exit
- d) Generate Stack Trace and Heap Dump
- c) Initiate Customer Support Tunnel
- a) About
  
- q) Quit to login screen

Enter menu item: x

```
admin@iea001 ~
$ cd /usr/local/postx/server/bin/
```

```
admin@iea001 /usr/local/postx/server/bin
$ ./managelicense.sh -importKey [license key from IronPort]
```

• 运行managelicense.sh脚本没有标志将允许您发现所有可用的参数。  
示例：

```
admin@iea001 /usr/local/postx/server/bin
$ ./managelicense.sh
USAGE:
managelicense.sh -list -importFile <file> -importKey <key> -prune -verbose help
-----
PARAMETERS -
help - Get this message.
list - Display the existing licenses.
importFile - Import the feature keys from the file specified as argument. Complete
path to the file should be specified.
importKey - Import the feature key specified in the argument.
prune - If this flag is present, then all expired keys to be
removed from the postx license file.
verbose - Enable for more verbose output.
-----
EXAMPLES -
TO LIST THE CURRENT LICENSES -
./managelicense.sh -list

TO IMPORT KEYS FROM A FILE -
./managelicense.sh -importFile /tmp/pxlicenses.txt

TO IMPORT A KEY FROM COMMAND LINE -
./managelicense.sh -importKey qeU1zEzyhl7868xa/fdsajflkasjdfdfaseasdfasdf==

TO PRUNE THE LICENSE FILE -
./managelicense.sh -prune

TO ENABLE VERBOSE MODE
./managelicense.sh -list -verbose
```